

ScaleIO v1.32

Lab Guide

August 2015

Copyright

Copyright © 1996, 2000, 2001, 2002, 2003, 2004, 2005, 2006, 2007, 2008, 2009, 2010, 2011, 2012, 2013, 2014, 2015 EMC Corporation. All Rights Reserved. EMC believes the information in this publication is accurate as of its publication date. The information is subject to change without notice.

THE INFORMATION IN THIS PUBLICATION IS PROVIDED “AS IS.” EMC CORPORATION MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND WITH RESPECT TO THE INFORMATION IN THIS PUBLICATION, AND SPECIFICALLY DISCLAIMS IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Use, copying, and distribution of any EMC software described in this publication requires an applicable software license.

EMC2, EMC, Data Domain, RSA, EMC Centera, EMC ControlCenter, EMC LifeLine, EMC OnCourse, EMC Proven, EMC Snap, EMC SourceOne, EMC Storage Administrator, Acartus, Access Logix, AdvantEdge, AlphaStor, ApplicationXtender, ArchiveXtender, Atmos, Authentica, Authentic Problems, Automated Resource Manager, AutoStart, AutoSwap, AVALONidm, Avamar, Captiva, Catalog Solution, C-Clip, Celerra, Celerra Replicator, Centera, CenterStage, CentraStar, ClaimPack, ClaimsEditor, CLARiiON, ClientPak, Codebook Correlation Technology, Common Information Model, Configuration Intelligence, Configuresoft, Connectrix, CopyCross, CopyPoint, Dantz, DatabaseXtender, Direct Matrix Architecture, DiskXtender, DiskXtender 2000, Document Sciences, Documentum, eInput, E-Lab, EmailXaminer, EmailXtender, Enginuity, eRoom, Event Explorer, FarPoint, FirstPass, FLARE, FormWare, Geosynchrony, Global File Virtualization, Graphic Visualization, Greenplum, HighRoad, HomeBase, InfoMover, Infoscapes, Infra, InputAccel, InputAccel Express, Invista, Ionix, ISIS, Max Retriever, MediaStor, MirrorView, Navisphere, NetWorker, nLayers, OnAlert, OpenScale, PixTools, Powerlink, PowerPath, PowerSnap, QuickScan, Rainfinity, RepliCare, RepliStor, ResourcePak, Retrospect, RSA, the RSA logo, SafeLine, SAN Advisor, SAN Copy, SAN Manager, Smarts, SnapImage, SnapSure, SnapView, SRDF, StorageScope, SupportMate, SymmAPI, SymmEnabler, Symmetrix, Symmetrix DMX, Symmetrix VMAX, TimeFinder, UltraFlex, UltraPoint, UltraScale, Unisphere, VMAX, Vblock, Viewlets, Virtual Matrix, Virtual Matrix Architecture, Virtual Provisioning, VisualSAN, VisualSRM, Voyence, VPLEX, VSAM-Assist, WebXtender, xPression, xPresso, YottaYotta, the EMC logo, and where information lives, are registered trademarks or trademarks of EMC Corporation in the United States and other countries.

All other trademarks used herein are the property of their respective owners.

© Copyright 2014 EMC Corporation. All rights reserved. Published in the USA.


Table of Contents

LAB EXERCISE 1: CONNECTING TO THE LAB ENVIRONMENT	3
LAB 1: TASK 1 – CONNECT TO LAB ENVIRONMENT	4
LAB EXERCISE 2-A: SCALEIO LINUX/WINDOWS INSTALLATION	8
LAB 2-A: TASK 1 - INSTALL SCALEIO INSTALLATION MANAGER	9
LAB 2-A: TASK 2 - CONNECT TO THE SCALEIO INSTALLATION MANAGER	10
LAB 2-A: TASK 3 - UPLOAD THE INSTALLATION PACKAGES	11
LAB 2-A: TASK 4 - UPLOAD THE CSV FILE.....	14
LAB 2-A: TASK 6 - ADD ADDITIONAL SDS USING INSTALLATION MANAGER	18
LAB EXERCISE 2-B: SCALEIO VMWARE INSTALLATION.....	22
LAB 2-B: TASK 1 - INSTALL SCALEIO PLUG-IN FOR VSPHERE	22
LAB 2-B: TASK 2 - INSTALL SVM TEMPLATE	26
LAB 2-B: TASK 3 - INSTALL SDC INTO THE KERNEL OF THE SELECTED ESXI SERVERS	28
LAB 2-B: TASK 4 – ADJUSTMENTS FOR LAB ENVIRONMENT	31
LAB 2-B: TASK 5 – DEPLOY SCALEIO ONTO VMWARE	35
LAB EXERCISE 3-A: SCALEIO CONFIGURATION AND MANAGEMENT	51
LAB 3-A: TASK 1 – GUI INTRODUCTION.....	51
LAB 3-A: TASK 2 – SCLI.....	55
LAB 3-A: TASK 3 – CREATE VOLUMES	59
LAB 3-A: TASK 4 – MAP VOLUMES TO SDC.....	62
LAB 3-A: TASK 4 – MAP VOLUMES TO WINDOWS SDC	67
LAB 3-A: TASK 5 – SNAPSHOT VOLUMES.....	70
LAB 3-A: TASK 6 – CONSISTENCY GROUPS.....	72
LAB 3-A: TASK 7 – INACTIVATION OF A PROTECTION DOMAIN.....	77
LAB 3-A: TASK 8 – RENAME THE PROTECTION DOMAIN	79
LAB 3-A: TASK 9 - RENAME STORAGE POOL	80
LAB 3-A: TASK 9 - RENAME STORAGE POOL	82
LAB EXERCISE 3-B: SCALEIO CONFIGURATION AND MANAGEMENT - ESXI CLUSTER	84
LAB 3-B: TASK 1 - EXPLORE VSPHERE PLUGIN.....	85
LAB 3-B: TASK 2 - CREATE AND MAP SCALEIO VOLUMES.....	86
LAB 3-B: TASK 3 - CREATE DATASTORES	90
LAB 3-B: TASK 4 - MIGRATE LIVE VM TO SCALEIO DATASTORE.....	93
LAB 3-B: TASK 5 - MIGRATE LIVE VM TO OTHER HOST.....	96
LAB EXERCISE 4: MONITORING AND PERFORMANCE TUNING	100
LAB 4: TASK 1 - MONITORING, REBALANCE AND REBUILD WHEN ADDING/REMOVING AN SDS	101
LAB 4: TASK 2 - ADJUSTING REBUILD AND REBALANCE POLICY.....	109
LAB 4: TASK 3 - CONFIGURING QoS FOR A VOLUME.....	112
LAB 4: TASK 4 - RAM CACHE DETERMINATION AND IMPLEMENTATION.....	115
LAB 4: TASK 5 - MONITORING SCALEIO-REPORTED EVENTS	119
LAB 4: TASK 6 - SET UP CENTRALIZED RSYSLOG SERVER FOR SCALEIO EVENT LOGGING	122
LAB EXERCISE 5-A: EXERCISING THE SCALEIO REST API.....	128





LAB 5-A: TASK 1 - VERIFY REST GATEWAY CONNECTION TO THE SCALEIO INSTANCE	129
LAB 5-A: TASK 2 - PREPARE THE FIREFOX REST CLIENT.....	130
LAB 5-A: TASK 3 - ISSUE "GET" AND "POST" REQUESTS TO SCALEIO	132
LAB X: END OF LAB.....	138




Lab Exercise 1: Connecting to the lab environment


Purpose:	Logon using your instructor-provided credentials to access the lab environment
Tasks:	✓ Log in to the vdc ✓ Login to the vCloud Director ✓ Copy vApp from catalog to workspace ✓ Start vApp ✓ Work within VM desktop
References:	ScaleIO Lab Diagram (graphically showing relevant details for all VMs within a student pod – refer to Page 2)




Lab 1: Task 1 – Connect to lab environment

Step	Action
1.	Open your browser to https://vdc.emc.com 
2.	Logon with the instructor provided credentials 
3.	Click on the link to the vCloud “Emerging Technology” datacenter (as shown) 
4.	An Internet Explorer window will appear (this is being presented by a remote Citrix server, not the local client). If you receive a warning about a plugin, Allow it 

Step	Action
5.	Log on with the same credentials as previously. 
6.	Click Add vApp from catalog 
7.	Select the ScaleIO I&M vApp then click Next 
8.	Let it select the default name and click Finish 



Step	Action
9.	Wait for the vApp to go from Creating to Stopped, then click the Start button.  
10.	Wait for it to go from Starting to Running, then click Open  
11.	The “dc” is the only system you should directly interact with from here. Click inside the desktop to access the console 

Step	Action
12.	Click inside the console to interact. Shown below are the functions of the icons.  Press Ctrl+Alt+Delete to sign in. 1. Send ctrl-alt-del to console 2. Expand console to fullscreen view 3. Expand window to match console desktop resolution




Lab Exercise 2-A: ScaleIO Linux/Windows Installation



Purpose:	Use the ScaleIO V Installation Manager (IM) graphical utility to install and expand a ScaleIO cluster on physical platforms running a mix of Linux and Windows.
Tasks:	✓ Connect to the dc desktop ✓ Install and configure the ScaleIO V Installation Manager ✓ Install a three-node ScaleIO cluster of Windows/Linux hosts, using the Installation Manager GUI ✓ Expand the cluster by adding one more Windows/Linux host as an SDS, also using Installation Manager
References:	ScaleIO Lab Diagram (graphically showing relevant details for all VMs within a student pod – refer to Page 2)

Lab 2-A: Task 1 - Install ScaleIO Installation Manager

Step	Action
	In this section, you will install and run the Installation Manager onto the DC system
13. 1	Log into the DC system. This is your access point for all other servers assigned to your pod.
14. 2	Open Windows Explorer to the following folder: C:\share\sw\Gateway_for_Windows 
15. 3	Double-click (run) the EMC-ScaleIO-Gateway....msi file. Proceed through the install, accepting the defaults and the license agreement. Enter the new admin password that will be used to access IM: P@ssw0rd  Once finished, close the Explorer windows and continue.



Lab 2-A: Task 2 - Connect to the ScaleIO Installation Manager

Step	Action
1.	<u>From the dc desktop</u>, use Firefox to access the URL for IM: https://dc.emc.edu  The screenshot shows the Firefox browser interface. At the top, there's a 'Mozilla Firefox' logo. Below it, a green bar with a yellow warning icon and the text 'Untrusted Connection' is visible. The address bar shows the URL 'https://dc.emc.edu' with a back arrow on the left.
2.	Accept the risks. Add the exception.   The first screenshot shows a dialog box titled 'I Understand the Risks'. It contains the text: 'If you understand what's going on, you can tell Firefox to start trusting this site's identification. Even if you trust the site, this error could mean that someone is tampering with your connection. Don't add an exception unless you know there's a good reason why this site doesn't use trusted identification.' There is a blue button labeled 'Add Exception...' with a mouse cursor pointing at it. The second screenshot shows a dialog box with a checked checkbox labeled 'Permanently store this exception'. At the bottom, there are two buttons: 'Confirm Security Exception' (highlighted in blue with a mouse cursor) and 'Cancel'.

Step	Action
3.	Logon as User: admin Password: P@ssw0rd  It is recommended to allow Firefox to save these credentials for convenience 

Lab 2-A: Task 3 - Upload the Installation Packages


Step	Action
	Before any installation can take place, the ScaleIO packages need to be uploaded to the installation manager gateway system.




Step	Action
1.	Along the top of the IM screen, click Packages.  The Manage Installation Packages window appears. Click Browse  You have not uploaded any packages to the Installation Manager.
2.	In the dialog box, open the c:\share\sw\Windows folder. Select all six MSI files found in that folder and click Open.  Hint: Click the first file, then hold Shift and click the last file to select them all at once.




Step	Action																																																	
3.	Click Upload. Manage Installation Packages Select the RPM / MSI packages to install on you A new installation requires the following package 6 files Upload Delete The uploaded installation packages appear in the file table: <table><caption>Packages uploaded to Installation Manager</caption><thead><tr><th>Type</th><th>OS</th><th>Linux flavor</th><th>Version</th><th>Latest</th><th>Size</th><th>File name</th></tr></thead><tbody><tr><td>TB</td><td>Windows</td><td>N/A</td><td>1.32-403.2</td><td>✓</td><td>1.19 MB</td><td>EMC-ScalIO-tb-1.32-403.2.msi</td></tr><tr><td>Callhome</td><td>Windows</td><td>N/A</td><td>1.32-403.2</td><td>✓</td><td>290.82 KB</td><td>EMC-ScalIO-callhome-1.32-403.2.msi</td></tr><tr><td>LIA</td><td>Windows</td><td>N/A</td><td>1.32-403.2</td><td>✓</td><td>745.47 KB</td><td>EMC-ScalIO-lia-1.32-403.2.msi</td></tr><tr><td>SDS</td><td>Windows</td><td>N/A</td><td>1.32-403.2</td><td>✓</td><td>1.43 MB</td><td>EMC-ScalIO-sds-1.32-403.2.msi</td></tr><tr><td>MDM</td><td>Windows</td><td>N/A</td><td>1.32-403.2</td><td>✓</td><td>3.72 MB</td><td>EMC-ScalIO-mdm-1.32-403.2.msi</td></tr><tr><td>SDC</td><td>Windows</td><td>N/A</td><td>1.32-403.2</td><td>✓</td><td>765.95 KB</td><td>EMC-ScalIO-sdc-1.32-403.2.msi</td></tr></tbody></table>	Type	OS	Linux flavor	Version	Latest	Size	File name	TB	Windows	N/A	1.32-403.2	✓	1.19 MB	EMC-ScalIO-tb-1.32-403.2.msi	Callhome	Windows	N/A	1.32-403.2	✓	290.82 KB	EMC-ScalIO-callhome-1.32-403.2.msi	LIA	Windows	N/A	1.32-403.2	✓	745.47 KB	EMC-ScalIO-lia-1.32-403.2.msi	SDS	Windows	N/A	1.32-403.2	✓	1.43 MB	EMC-ScalIO-sds-1.32-403.2.msi	MDM	Windows	N/A	1.32-403.2	✓	3.72 MB	EMC-ScalIO-mdm-1.32-403.2.msi	SDC	Windows	N/A	1.32-403.2	✓	765.95 KB	EMC-ScalIO-sdc-1.32-403.2.msi
Type	OS	Linux flavor	Version	Latest	Size	File name																																												
TB	Windows	N/A	1.32-403.2	✓	1.19 MB	EMC-ScalIO-tb-1.32-403.2.msi																																												
Callhome	Windows	N/A	1.32-403.2	✓	290.82 KB	EMC-ScalIO-callhome-1.32-403.2.msi																																												
LIA	Windows	N/A	1.32-403.2	✓	745.47 KB	EMC-ScalIO-lia-1.32-403.2.msi																																												
SDS	Windows	N/A	1.32-403.2	✓	1.43 MB	EMC-ScalIO-sds-1.32-403.2.msi																																												
MDM	Windows	N/A	1.32-403.2	✓	3.72 MB	EMC-ScalIO-mdm-1.32-403.2.msi																																												
SDC	Windows	N/A	1.32-403.2	✓	765.95 KB	EMC-ScalIO-sdc-1.32-403.2.msi																																												
4.	Repeat Steps 2 and 3 using the c:\share\sw\RHEL6 folder, and upload the six RPMs found in that folder. <table><thead><tr><th>File name</th></tr></thead><tbody><tr><td>EMC-ScalIO-sds-1.32-403.2.msi</td></tr><tr><td>EMC-ScalIO-tb-1.32-403.2.el6.x86_64.rpm</td></tr><tr><td>EMC-ScalIO-sds-1.32-403.2.el6.x86_64.rpm</td></tr><tr><td>EMC-ScalIO-tb-1.32-403.2.msi</td></tr><tr><td>EMC-ScalIO-lia-1.32-403.2.el6.x86_64.rpm</td></tr><tr><td>EMC-ScalIO-lia-1.32-403.2.msi</td></tr><tr><td>EMC-ScalIO-sdc-1.32-403.2.el6.x86_64.rpm</td></tr><tr><td>EMC-ScalIO-mdm-1.32-403.2.msi</td></tr><tr><td>EMC-ScalIO-sdc-1.32-403.2.msi</td></tr><tr><td>EMC-ScalIO-callhome-1.32-403.2.el6.x86_64.rpm</td></tr></tbody></table><table><tbody><tr><td>EMC-ScalIO-callhome-1.32-403.2.msi</td></tr><tr><td>EMC-ScalIO-mdm-1.32-403.2.el6.x86_64.rpm</td></tr></tbody></table>	File name	EMC-ScalIO-sds-1.32-403.2.msi	EMC-ScalIO-tb-1.32-403.2.el6.x86_64.rpm	EMC-ScalIO-sds-1.32-403.2.el6.x86_64.rpm	EMC-ScalIO-tb-1.32-403.2.msi	EMC-ScalIO-lia-1.32-403.2.el6.x86_64.rpm	EMC-ScalIO-lia-1.32-403.2.msi	EMC-ScalIO-sdc-1.32-403.2.el6.x86_64.rpm	EMC-ScalIO-mdm-1.32-403.2.msi	EMC-ScalIO-sdc-1.32-403.2.msi	EMC-ScalIO-callhome-1.32-403.2.el6.x86_64.rpm	EMC-ScalIO-callhome-1.32-403.2.msi	EMC-ScalIO-mdm-1.32-403.2.el6.x86_64.rpm																																				
File name																																																		
EMC-ScalIO-sds-1.32-403.2.msi																																																		
EMC-ScalIO-tb-1.32-403.2.el6.x86_64.rpm																																																		
EMC-ScalIO-sds-1.32-403.2.el6.x86_64.rpm																																																		
EMC-ScalIO-tb-1.32-403.2.msi																																																		
EMC-ScalIO-lia-1.32-403.2.el6.x86_64.rpm																																																		
EMC-ScalIO-lia-1.32-403.2.msi																																																		
EMC-ScalIO-sdc-1.32-403.2.el6.x86_64.rpm																																																		
EMC-ScalIO-mdm-1.32-403.2.msi																																																		
EMC-ScalIO-sdc-1.32-403.2.msi																																																		
EMC-ScalIO-callhome-1.32-403.2.el6.x86_64.rpm																																																		
EMC-ScalIO-callhome-1.32-403.2.msi																																																		
EMC-ScalIO-mdm-1.32-403.2.el6.x86_64.rpm																																																		
5.	When you are finished uploading the files, click Proceed to Install > to continue. Proceed to Install >																																																	



Lab 2-A: Task 4 - Upload the CSV File

Step	Action																												
	The CSV file provides the installation manager system with the data required to complete the installation. It includes the host information, along with roles, networking, devices etc.																												
1.	The browser goes to the Installation Topology screen. Click the Browse button.: Provide Installation Topology Upload an installation .csv file that describes the desired topology of the new ScaleIO system. Browse ... New installation Upload installation CSV																												
2.	Select the following file C:\share\misc\ ScaleIO_Initial_Config.csv. Click Open. The file name appears in place of the Browse button.																												
3.	For your reference, here is the file in Microsoft Excel: <table><tr><th>IPs</th><th>Password</th><th>Operating System</th><th>Is MDM/TB</th><th>Is SDS</th><th>SDS Device List</th><th>Is SDC</th></tr><tr><td>192.168.1.10</td><td>P0ssw0rd</td><td>linux</td><td>Primary</td><td>Yes</td><td>/dev/sdb</td><td>Yes</td></tr><tr><td>192.168.1.11</td><td>P0ssw0rd</td><td>linux</td><td>Secondary</td><td>Yes</td><td>/dev/sdb</td><td>Yes</td></tr><tr><td>192.168.1.12</td><td>P0ssw0rd</td><td>linux</td><td>TB</td><td>Yes</td><td>/dev/sdb</td><td>Yes</td></tr></table> Note: For your convenience, this CSV file has been pre-populated with all the relevant data for your specific ScaleIO hosts. In a real deployment, you will need to manually edit the configuration file suitably, before uploading it to the Installation Manager.	IPs	Password	Operating System	Is MDM/TB	Is SDS	SDS Device List	Is SDC	192.168.1.10	P0ssw0rd	linux	Primary	Yes	/dev/sdb	Yes	192.168.1.11	P0ssw0rd	linux	Secondary	Yes	/dev/sdb	Yes	192.168.1.12	P0ssw0rd	linux	TB	Yes	/dev/sdb	Yes
IPs	Password	Operating System	Is MDM/TB	Is SDS	SDS Device List	Is SDC																							
192.168.1.10	P0ssw0rd	linux	Primary	Yes	/dev/sdb	Yes																							
192.168.1.11	P0ssw0rd	linux	Secondary	Yes	/dev/sdb	Yes																							
192.168.1.12	P0ssw0rd	linux	TB	Yes	/dev/sdb	Yes																							
4.	Click the Upload installation CSV button. Provide Installation Topology Upload an installation .csv file that describes the desired topology of the new ScaleIO system. ScaleIO_Initial_Config.csv New installation Upload installation CSV																												

Step	Action
5.	At the top of the installation configuration screen, set the MDM and LIA passwords to P@ssw0rd. Accept the license Agreement, and remove the check for Call Home (which we will not be configuring during this lab exercise).  The screenshot shows the 'Installation Configuration' screen. At the top, a green banner states 'The CSV file was successfully processed'. Below this, a message says 'Review the configuration, enter passwords and other options, then start the installation.' The 'Credentials Configuration' section has two password fields for 'MDM Password' and 'LIA Password', both of which are annotated with red arrows pointing to the text 'P@ssw0rd' written above them. The 'License' section has a checked checkbox for 'I accept the terms of the End User License Agreement (mandatory)' and a link to 'View EULA'. The 'Advanced' section has an unchecked checkbox for 'Set advanced options (optional)'. The 'Syslog' section has an unchecked checkbox for 'Configure the sending of syslog events (optional)'. The 'Call Home' section has an unchecked checkbox for 'Configure call home (optional)', which is annotated with a red arrow pointing to it.

Step	Action
6.	Confirm the topology (but don't change anything).  Click 
7.	Click on either monitor screen to bring up the installation monitor 




Step	Action
8.	The installation performs the following phases: upload, install, and configure. Note: If you get an error message during the process, you can retry the failed operations. 
9.	The Query phase starts automatically. When it finishes without error, close the “completed” box, and click Start upload phase 
10.	When the Upload phase finishes without error, close the “completed” box, and click Start install phase 



Step	Action
11.	When the Install phase finishes without error, close the “completed” box, and click Start Configure phase 
12.	Configure is the final phase. When it finished, the installation and configuration is complete on all nodes. Click Mark Operation Completed. 

Lab 2-A: Task 6 - Add additional SDS using Installation Manager

Step	Action
	In this section you will use a csv file to add a single SDS system to the cluster you’ve just constructed
1.	Within the installation GUI, Click on the Install box 

Step	Action																																																																																				
2.	In the provide installation topology screen, click Add to existing system in the middle, then click Browse Provide Installation Topology Upload an installation .csv file that describes the desired topology of the new ScaleIO Browse ... Add to existing sys. Upload installation CSV																																																																																				
3.	Browse to c:\share\misc, and select ScaleIO_Add_SDSWin2.csv file << share >> misc > New folder Name GPG-RPM-KEY Python_Installation_Modules_Download ScaleIO_Add_SDSWin2.csv Here are the contents of the file <table><tr><th>Domain</th><th>Username</th><th>Password</th><th>Operating System</th><th>Is MDM/TB</th><th>MDM Mgmt IP</th></tr><tr><td>localhost</td><td>administrator</td><td>P@sswOrd</td><td>windows</td><td>No</td><td></td></tr><tr><td></td><td>root</td><td>P@sswOrd</td><td>linux</td><td>Primary</td><td></td></tr><tr><td></td><td>root</td><td>P@sswOrd</td><td>linux</td><td>Secondary</td><td></td></tr><tr><td></td><td>root</td><td>P@sswOrd</td><td>linux</td><td>TB</td><td></td></tr></table> <table><tr><th>MDM IPs</th><th>Is SDS</th><th>SDS Name</th><th>SDS All IPs</th><th>SDS-SDS Only IPs</th><th>SDS-SDC Only IPs</th></tr><tr><td></td><td>Yes</td><td>SDSWin2</td><td>192.168.1.21</td><td></td><td></td></tr><tr><td>192.168.1.10</td><td></td><td></td><td></td><td></td><td></td></tr><tr><td>192.168.1.11</td><td></td><td></td><td></td><td></td><td></td></tr><tr><td>192.168.1.12</td><td></td><td></td><td></td><td></td><td></td></tr></table> <table><tr><th>Protection Domain</th><th>Fault Set</th><th>SDS Device List</th><th>SDS Pool List</th><th>Optimize IOPS</th><th>Is SDC</th></tr><tr><td>default</td><td></td><td>e</td><td>default</td><td>No</td><td>No</td></tr><tr><td></td><td></td><td></td><td></td><td></td><td></td></tr><tr><td></td><td></td><td></td><td></td><td></td><td></td></tr></table> Click Upload	Domain	Username	Password	Operating System	Is MDM/TB	MDM Mgmt IP	localhost	administrator	P@sswOrd	windows	No			root	P@sswOrd	linux	Primary			root	P@sswOrd	linux	Secondary			root	P@sswOrd	linux	TB		MDM IPs	Is SDS	SDS Name	SDS All IPs	SDS-SDS Only IPs	SDS-SDC Only IPs		Yes	SDSWin2	192.168.1.21			192.168.1.10						192.168.1.11						192.168.1.12						Protection Domain	Fault Set	SDS Device List	SDS Pool List	Optimize IOPS	Is SDC	default		e	default	No	No												
Domain	Username	Password	Operating System	Is MDM/TB	MDM Mgmt IP																																																																																
localhost	administrator	P@sswOrd	windows	No																																																																																	
	root	P@sswOrd	linux	Primary																																																																																	
	root	P@sswOrd	linux	Secondary																																																																																	
	root	P@sswOrd	linux	TB																																																																																	
MDM IPs	Is SDS	SDS Name	SDS All IPs	SDS-SDS Only IPs	SDS-SDC Only IPs																																																																																
	Yes	SDSWin2	192.168.1.21																																																																																		
192.168.1.10																																																																																					
192.168.1.11																																																																																					
192.168.1.12																																																																																					
Protection Domain	Fault Set	SDS Device List	SDS Pool List	Optimize IOPS	Is SDC																																																																																
default		e	default	No	No																																																																																

Step	Action
4.	On the Review Installation Configuration screen: Enter admin P@ssw0rd for MDM credentials, and P@ssw0rd for the LIA password. Accept the license. Do not configure call home. 
5.	Take a moment to review the displayed information regarding the new SDS. 
6.	Click Start Installation 
7.	Click Monitor 


Step	Action
8.	The phases will be identical to the previous phases. If you see an error or aborted operation, click Retry Failed. Otherwise, follow the instructions similar to the previous section,
9.	When the configure phase completes, click mark operation completed 
10.	Minimize the browser and Click on the "lnx-1" icon (it will automatically connect to lnx-1 via putty and logon as root / P@ssw0rd) 
11.	Run the following commands: <pre>scli --login --username admin --password P@ssw0rd scli --query_cluster</pre> 




End of Lab Exercise 2-A


Lab Exercise 2-B: ScaleIO VMware Installation


Purpose:	Use the ScaleIO vSphere Web Client plug-in to install and expand a ScaleIO cluster on the VMware ESXi platform.
Tasks:	✓ Install the ScaleIO plug-in ✓ Install a three-node ScaleIO cluster of VMware ESX hosts using the ScaleIO Deployment Wizard ✓ Assess validity and completeness of the installed configuration, including: executing basic ScaleIO commands on one of the deployed SVM appliances

Lab 2-B: Task 1 - Install ScaleIO Plug-in for vSphere

Step	Action
	This task has you installing the ScaleIO plugin into the vCenter server. It is handled via a powercli script.
1.	Click on the PowerCLI icon on the desktop 
2.	Open an explorer window to c:\share\sw\VMware\Plugin 


Step	Action
3.	Drag the ScaleIO...ps1 file into the PowerCLI window  <pre>PowerCLI C:\Program Files (x86)\VMware\Infrastructure\vsphere PowerCLI> C:\share\sw\VMware\Plugin\ScaleIOPluginSetup-1.32-403.2.ps1</pre>
4.	Hit enter to launch the ps1 file. Enter the following information at the prompts: - vCenter vc.emc.edu - Username root - Password P@ssw0rd  <pre>PowerCLI C:\Program Files (x86)\VMware\Infrastructure\vsphere PowerCLI> .\ScaleIOPluginSetup-1.32-403.2.ps1 cmdlet ScaleIOPluginSetup-1.32-403.2.ps1 Supply values for the following variables: (Type !? for Help.) vCenter: vc.emc.edu Username: root Password: *****</pre>
5.	Enter 1 to register the plugin, y to continue, and s for Standard registration  <pre>Choose mode: 1 - Register ScaleIO plug-in 2 - Unregister ScaleIO plug-in 3 - Create SVM template 4 - Exit the script : 1 Welcome to ScaleIO Plugin Register Utility Important notice to users upgrading to ScaleIO release 1.32: 1. ESXi 5.1 is no longer supported. ESXi 5.5 and above are supported. 2. Running SDC within an SVM is no longer supported. SDC must be installed in the ESXi host. If your configuration isn't supported, DO NOT UPGRADE. Contact Support for additional info and further assistance. Do you wish to continue? Y / N: y Do you want to run the Standard or Advanced registration? [s/a]: s Waiting for internal server to load (attempt 1)...</pre>

Step	Action
6.	After several seconds you will prompted to log in to the vSphere client (do not hit enter yet) <pre> WARNING: THE DEFAULT BEHAVIOR UPON INVALID SERVER CERTIFICATE WILL CHANGE IN A FUTURE RELEASE. To ensure scripts are not affected by the change, use Set-PowerCLIConfiguration to set a value for the InvalidCertificateAction option. Successfully connected to vCenter vc.emc.edu Registering ScaleIO extension... Log out, and then log back in to vSphere web client. The plugin is downloaded upon login to the vSphere web client. After you have logged back in, press ENTER. </pre>
7.	Connect to the vSphere web client by using the desktop icon (or by pointing firefox to https://vc.emc.edu:9443) 
8.	Logon as root P@ssw0rd 



Step	Action
9.	From the vSphere home screen, click on the Home tab – notice the EMC ScaleIO plugin (no need to click on it). 
10.	Return to PowerCLI and hit Enter to continue <pre data-bbox="215 1050 1060 1297"> Log out, and then log back in to vSphere web client. r you have logged back in, press ENTER. Choose mode: 1 - Register ScaleIO plug-in 2 - Unregister ScaleIO plug-in 3 - Create SVM template 4 - Exit the script : _ </pre> Do not exit PowerCLI.

Lab 2-B: Task 2 - Install SVM Template



Step	Action
	This task has you continuing to work within the ScaleIO Registration script, to create a ScaleIO Virtual Machine (SVM) template. This template will be later used by the ScaleIO deployment wizard to create virtual machines enabling MDM, SDS, LIA, and Gateway functionality. You will need to assign it to a specified datacenter, specified datastore(s), and select the “ova” file to be used.
1.	Enter three from the PowerCLI script menu to start the template registration <pre>Choose mode: 1 - Register ScaleIO plug-in 2 - Unregister ScaleIO plug-in 3 - Create SVM template 4 - Exit the script : 3 Disconnecting from the vCenter vc.emc.edu... Welcome to ScaleIO Plugin Create SVM Template Utility</pre>
2.	Enter Datacenter as the datacenter <pre>Welcome to ScaleIO Plugin Create SVM Template Utility Enter a datacenter name: Datacenter Datacenter is: Datacenter</pre>



Step	Action
3.	When prompted for the location of the ova file, open an explorer window and drag the following file into the powercli window, and hit enter: C:\share\sw\VMware\ScaleIOVM...ova <i>(or you can always just type it in as shown)</i>  Enter the path of the SVM's OVA: C:\share\sw\VMware\ScaleIOVM_1.32.403.2.ova
4.	When prompted for a datastore, enter DS30. When prompted for a second datastore, just hit enter (to skip). <pre> Enter a list of datastores (max 8), each needed to have at least 10GB ated. To finish, enter a blank datastore: Datastores - 1 : DS30 Datastores - 2 : <enter> datastores: DS30 </pre>
5.	The process will begin immediately, and will take several minutes. When you are returned to the script menu, enter 4 to exit the script. Then type exit to exit PowerCLI <pre> The template EMC ScaleIO SVM Template (v1.32.403.2) 1 was successfully created Deleting temporary SVM... Temporary SVM was successfully deleted Choose mode: 1 - Register ScaleIO plug-in 2 - Unregister ScaleIO plug-in 3 - Create SVM template 4 - Exit the script : 4 Disconnecting from the vCenter vc.emc.edu... PowerCLI C:\Program Files (x86)\VMware\Infrastructure\vsphere PowerCLI> exit </pre>

Lab 2-B: Task 3 - Install SDC into the kernel of the selected ESXi servers

Step	Action
	In this task, you will install the SDC onto the kernels of the 3 ESXi hosts. It is done through an installer included with the ScaleIO plugin. It requires a reboot of the ESXi server.
1.	In the vSphere Web Client (root P@ssw0rd), Home screen, click on the ScaleIO plugin 
2.	Under Basic tasks, click on Install SDC on ESX 



Step	Action																																																			
3.	Select all three ESXi servers, enter P@ssw0rd as the password (click show passwords to help ensure it is entered correctly), and click Install Select the ESXs on which you want to install the SDC <table><thead><tr><th>ESX</th><th>Install SDC</th><th>ESX Root Password</th></tr></thead><tbody><tr><td> vCenter</td><td>☐</td><td> </td></tr><tr><td> Datacenter</td><td>☐</td><td> </td></tr><tr><td> SIO</td><td>☐</td><td> </td></tr><tr><td> 192.168.1.30</td><td>☒</td><td>P@ssw0rd</td></tr><tr><td> 192.168.1.31</td><td>☒</td><td>P@ssw0rd</td></tr><tr><td> 192.168.1.32</td><td>☒</td><td>P@ssw0rd</td></tr></tbody></table> ☒ Show passwords Install Cancel <tr><td>4.</td><td> The installation will commence. When it is finished, click Finish SDC installation progress: <table><thead><tr><th>ESX</th><th>1 ▲</th><th>Status</th></tr></thead><tbody><tr><td>192.168.1.30</td><td></td><td> Running</td></tr><tr><td>192.168.1.31</td><td></td><td> Running</td></tr><tr><td>192.168.1.32</td><td></td><td> Running</td></tr></tbody></table> Install SDC on ESX SDC installation progress: <table><thead><tr><th>ESX</th><th>1 ▲</th><th>Status</th><th>Error</th></tr></thead><tbody><tr><td>192.168.1.30</td><td></td><td> Finished</td><td></td></tr><tr><td>192.168.1.31</td><td></td><td> Finished</td><td></td></tr><tr><td>192.168.1.32</td><td></td><td> Finished</td><td></td></tr></tbody></table> Installing SDC on ESXs finished successfully Finish Close </td></tr>	ESX	Install SDC	ESX Root Password	vCenter	☐		Datacenter	☐		SIO	☐		192.168.1.30	☒	P@ssw0rd	192.168.1.31	☒	P@ssw0rd	192.168.1.32	☒	P@ssw0rd	4.	The installation will commence. When it is finished, click Finish SDC installation progress: <table><thead><tr><th>ESX</th><th>1 ▲</th><th>Status</th></tr></thead><tbody><tr><td>192.168.1.30</td><td></td><td> Running</td></tr><tr><td>192.168.1.31</td><td></td><td> Running</td></tr><tr><td>192.168.1.32</td><td></td><td> Running</td></tr></tbody></table> Install SDC on ESX SDC installation progress: <table><thead><tr><th>ESX</th><th>1 ▲</th><th>Status</th><th>Error</th></tr></thead><tbody><tr><td>192.168.1.30</td><td></td><td> Finished</td><td></td></tr><tr><td>192.168.1.31</td><td></td><td> Finished</td><td></td></tr><tr><td>192.168.1.32</td><td></td><td> Finished</td><td></td></tr></tbody></table> Installing SDC on ESXs finished successfully Finish Close	ESX	1 ▲	Status	192.168.1.30		Running	192.168.1.31		Running	192.168.1.32		Running	ESX	1 ▲	Status	Error	192.168.1.30		Finished		192.168.1.31		Finished		192.168.1.32		Finished	
ESX	Install SDC	ESX Root Password																																																		
vCenter	☐																																																			
Datacenter	☐																																																			
SIO	☐																																																			
192.168.1.30	☒	P@ssw0rd																																																		
192.168.1.31	☒	P@ssw0rd																																																		
192.168.1.32	☒	P@ssw0rd																																																		
4.	The installation will commence. When it is finished, click Finish SDC installation progress: <table><thead><tr><th>ESX</th><th>1 ▲</th><th>Status</th></tr></thead><tbody><tr><td>192.168.1.30</td><td></td><td> Running</td></tr><tr><td>192.168.1.31</td><td></td><td> Running</td></tr><tr><td>192.168.1.32</td><td></td><td> Running</td></tr></tbody></table> Install SDC on ESX SDC installation progress: <table><thead><tr><th>ESX</th><th>1 ▲</th><th>Status</th><th>Error</th></tr></thead><tbody><tr><td>192.168.1.30</td><td></td><td> Finished</td><td></td></tr><tr><td>192.168.1.31</td><td></td><td> Finished</td><td></td></tr><tr><td>192.168.1.32</td><td></td><td> Finished</td><td></td></tr></tbody></table> Installing SDC on ESXs finished successfully Finish Close	ESX	1 ▲	Status	192.168.1.30		Running	192.168.1.31		Running	192.168.1.32		Running	ESX	1 ▲	Status	Error	192.168.1.30		Finished		192.168.1.31		Finished		192.168.1.32		Finished																								
ESX	1 ▲	Status																																																		
192.168.1.30		Running																																																		
192.168.1.31		Running																																																		
192.168.1.32		Running																																																		
ESX	1 ▲	Status	Error																																																	
192.168.1.30		Finished																																																		
192.168.1.31		Finished																																																		
192.168.1.32		Finished																																																		



Step	Action
5.	Click OK on the popup To complete the installation, restart the ESXs. 
6.	On the left side of the vsphere home page, click on Hosts and Clusters 
7.	Right-click on the 192.168. ESX server, and click Reboot. Then click OK on the popup to reboot the host  Reboot the selected host? 

Step	Action
8.	Repeat previous step for the other two ESX servers. Wait until all three servers have rebooted before continuing. They will be unresponsive for a minute or two. Wait until they appear “normal” (bottom screen shot) before continuing. You can click the refresh button in the vSphere Web Client for a more accurate update   

Lab 2-B: Task 4 – Adjustments for lab environment

Step	Action
	This task has you making adjustments necessary to support the lab environment. These are not the recommended settings in a production environment. In order to create a scalable lab allowing multiple concurrent connections, we are using Virtual ESXi servers. These allow for full ScaleIO functionality, but require minor settings changes. One is to “allow vmdk creation”. Normally, the selected SDS devices are passed to the SVM as raw devices (using VMware’s RDM capability). This will not work here. This option formats the devices with VMFS, configured as a standard Datastore, and creates a single VMDK on each, which is then presented as a virtual disk to the SVM. Because the VMDK’s use nearly all the available space on the VMFS, expect to see warnings in the vSphere client about datastore free space. You can ignore these warnings. The other adjustment speeds up the deployment time. When VMDK’s are created, the “eager zeroed” option is the default. This writes a “0” to all bits of the VMDK. While it creates a more efficient VMDK in production, the time to write this is excessive. Disabling this speeds up the process by 20 minutes or more.

Step	Action
1.	Click on the home button and return to the ScaleIO plugin 
2.	Click on Advanced Settings on the right 

Step	Action
3.	Check Enable VMDK creation and click OK 
4.	Minimize the browser, and open a connection to the vCenter appliance directly, by clicking on the icon on the desktop (click Yes if you encounter a security prompt).  <i>(it will launch a putty connection and logon as root P@ssw0rd, automatically)</i>
5.	Enter the following command to edit the settings file for the deployment wizard <pre>vi /etc/vmware/vsphere-client/vc-packages/scaleio/serverConfig.cfg</pre> 

Step	Action
6.	Insert the following line into the file as shown <pre><vmdk_eager_zeroed>false</vmdk_eager_zeroed></pre> BEFORE <pre><?xml version="1.0" encoding="UTF-8" standalone="no"?> <server_configuration> <general> <allow_vmdk_creation>true</allow_vmdk_creation> <allow_rdm_on_non_parallel_scsi>false</allow_rdm <allow_non_clustered_ScaleIO_system>false</allow <datastore_spare_capacity_percentage>10</datasto <svm_reserved_size_in_gb>8</svm_reserved_size_in <paralellism_limit>100</paralellism_limit> <support_unsigned_vib>false</support_unsigned_vi <vmware_timeout_in_minutes>2</vmware_timeout_in_ </general> </server_configuration></pre> AFTER <pre><?xml version="1.0" encoding="UTF-8" standalone="no"?> <server_configuration> <general> <vmdk_eager_zeroed>false</vmdk eager_zeroed> <allow_vmdk_creation>true</allow_vmdk_creation> <allow_rdm_on_non_parallel_scsi>false</allow_rdm <allow_non_clustered_ScaleIO_system>false</allow <datastore_spare_capacity_percentage>10</datasto <svm_reserved_size_in_gb>8</svm_reserved_size_in <paralellism_limit>100</paralellism_limit> <support_unsigned_vib>false</support_unsigned_vi <vmware_timeout_in_minutes>2</vmware_timeout_in_ </general> </server_configuration></pre>
7.	Save and exit the file (<Esc> : w q <Enter>)

Step	Action
8.	Return the ScaleIO Plugin session EMC ScaleIO v1.32-403.2 EMC ScaleIO is software that creates a virtual SAN from local server-based storage to deliver elastic and scalable performance and capacity on demand. ScaleIO converges storage and compute resources, scaling from tens to Basic tasks - Install SDC on ESX - Deploy ScaleIO environment - Register ScaleIO system

Lab 2-B: Task 5 – Deploy ScaleIO onto VMware

Step	Action
	This task has you entering all the values and completing the deployment. Here is a summary: - New ScaleIO Cluster with a name of “SIO-VMW” and P@ssw0rd as the admin password - o One protection domain “PD1” - o One Storage Pool “SP1” - o A Gateway VM on 192.168. - MDM - o 192.168. → Primary - o 192.168.1.31 → Secondary - o 192.168.1.32 → Tie Breaker - SDS - o All three ESXi servers - o 1 disk added from each SDS (105GB, VMDK created) - SDC - o All three ESXi servers - o SCSI LUN number comparison Disabled - Networking - o ScaleIO management traffic on existing 192.168.1.x network - o Data traffic on new 192.168.2.x network

Step	Action
1.	From the ScaleIO Plugin page, click Deploy ScaleIO environment Basic tasks Install SDC on ESX Deploy ScaleIO environment Register ScaleIO system
2.	On the Select Installation Type screen, leave at the default (Create new ScaleIO system), and click Next Select an installation option: ☒ Create new ScaleIO system ☐ Add servers to a registered ScaleIO system: ☐ Deploy ScaleIO Gateway for a registered ScaleIO system:
3.	On the Confirm license screen, Click I agree... and click Next this Agreement shall govern the relationship of the parties with regard to the subject matter in this Agreement and are waiving any rights to the maximum extent permitted by applicable law ☒ I agree to license terms and conditions
4.	On the Create new system screen, enter SIO-VMW as the system name, enter and confirm P@ssw0rd as the password, and click Next Enter a name for the new ScaleIO system: System name: SIO-VMW Enter a password for the "admin" user: Enter a password ***** Confirm the password *****

Step	Action
5.	On the Add ESX hosts to cluster screen, Select vCenter as the vCenter server, select all three ESX hosts (you can select any parent object to do this as well), and click Next. Select the vCenter on which to install the ScaleIO system: vCenter Select at least 3 ESX hosts for the ScaleIO system: ▼ vCenter ▼ Datacenter ▼ SIO 192.168.1.30 192.168.1.31 192.168.1.32
6.	On the Select management components screen, assign the roles as shown below, and click Next Select an ESX host for the Primary MDM virtual machine: 192.168.1.30 Select an ESX host for the Secondary MDM virtual machine: 192.168.1.31 Select an ESX host for the Tie Breaker virtual machine: 192.168.1.32
7.	On the Configure Call Home screen, remove the check from Configure Call Home, and click Next Configure Call Home, Syslog, and DNS servers (optional): ☐ Configure Call Home * SMTP server: localhost

Step	Action				
8.	On the Configure protection domain screen, Enter PD1, click Add (it will appear below), and click Next. Add new Protection Domain to ScaleIO system: Protection Domain name: PD1 RAM Read Cache size per SDS: 128 MB ▲ ▼ Add Existing Protection Domains in ScaleIO system: <table border="1" data-bbox="232 804 1092 930"> <thead> <tr> <th data-bbox="248 825 711 867">Protection Domain Name</th><th data-bbox="711 825 1084 867">RAM Read Cache Size (in MB)</th></tr> </thead> <tbody> <tr> <td data-bbox="248 867 711 919">PD1</td><td data-bbox="711 867 1084 919">128</td></tr> </tbody> </table>	Protection Domain Name	RAM Read Cache Size (in MB)	PD1	128
Protection Domain Name	RAM Read Cache Size (in MB)				
PD1	128				
9.	On the Configure Storage Pools screen, enter SP1 as the storage pool name (under protection domain PD1), click Add (it will appear below), and click Next. Create a new Storage Pool in the ScaleIO system: Storage Pool name: SP1 Parent Protection Domain: PD1 ▼ <input data-bbox="264 1350 289 1371" type="checkbox"/> Enable zero padding  Add New and existing Protection Domains and Storage Pools: ▼  PD1  SP1				




Step	Action																														
10.	On the Create Fault Sets screen, do not enter a fault set, and click Next Create new Fault Sets for the ScaleIO system (optional): Fault Set name: Select Protection Domain: PD1																														
11.	On the Add SDS screen, select all three ESX hosts (can also select a parent object), and click Next. Select ESXs to add as SDSs to ScaleIO system: <table><thead><tr><th>Cluster/ESX</th><th>SDS</th><th>Protection Domain</th><th>Fault Set</th><th>Optimize for Flash</th></tr></thead><tbody><tr><td>▼ Datacenter</td><td>☒</td><td>PD1 ▼</td><td> </td><td>☒</td></tr><tr><td>▼ SIO</td><td>☒</td><td>PD1 ▼</td><td> </td><td>☐</td></tr><tr><td>192.168.1.30</td><td>☒</td><td>PD1 ▼</td><td> </td><td>☐</td></tr><tr><td>192.168.1.31</td><td>☒</td><td>PD1 ▼</td><td> </td><td>☐</td></tr><tr><td>192.168.1.32</td><td>☒</td><td>PD1 ▼</td><td> </td><td>☐</td></tr></tbody></table>	Cluster/ESX	SDS	Protection Domain	Fault Set	Optimize for Flash	▼ Datacenter	☒	PD1 ▼		☒	▼ SIO	☒	PD1 ▼		☐	192.168.1.30	☒	PD1 ▼		☐	192.168.1.31	☒	PD1 ▼		☐	192.168.1.32	☒	PD1 ▼		☐
Cluster/ESX	SDS	Protection Domain	Fault Set	Optimize for Flash																											
▼ Datacenter	☒	PD1 ▼		☒																											
▼ SIO	☒	PD1 ▼		☐																											
192.168.1.30	☒	PD1 ▼		☐																											
192.168.1.31	☒	PD1 ▼		☐																											
192.168.1.32	☒	PD1 ▼		☐																											
12.	On the Add devices to SDS screen, select the first ESX host (192.168.) as shown. Do NOT click Next. ▼ Datacenter ▼ SIO 192.168.1.30 192.168.1.31 192.168.1.32																														

Step	Action																								
13.	Click on the Select Devices tab, select the C0:T1:L0 device, click Add Device and Create VM... (VMDK). Do not click Next. Information Select devices Replicate selection <table><tr><th>Device Name</th><th>Free (GB)</th><th>SSD</th><th>Add Device</th><th>Create VM...</th><th>Storage Pool</th></tr><tr><td>mpx.vmhba1:C0:T2:L0</td><td>105</td><td></td><td>☐</td><td>☐</td><td>SP1 (PD1) ▾</td></tr><tr><td>mpx.vmhba1:C0:T1:L0</td><td>105</td><td></td><td>☒</td><td>☒</td><td>SP1 (PD1) ▾</td></tr><tr><td>mpx.vmhba1:C0:T0:L0</td><td>33</td><td></td><td>☐</td><td>☒</td><td>SP1 (PD1) ▾</td></tr></table>	Device Name	Free (GB)	SSD	Add Device	Create VM...	Storage Pool	mpx.vmhba1:C0:T2:L0	105		☐	☐	SP1 (PD1) ▾	mpx.vmhba1:C0:T1:L0	105		☒	☒	SP1 (PD1) ▾	mpx.vmhba1:C0:T0:L0	33		☐	☒	SP1 (PD1) ▾
Device Name	Free (GB)	SSD	Add Device	Create VM...	Storage Pool																				
mpx.vmhba1:C0:T2:L0	105		☐	☐	SP1 (PD1) ▾																				
mpx.vmhba1:C0:T1:L0	105		☒	☒	SP1 (PD1) ▾																				
mpx.vmhba1:C0:T0:L0	33		☐	☒	SP1 (PD1) ▾																				

Step	Action																																																
14.	Repeat the previous two steps for 192.168.1.31, and 192.168.1.32. Then, click Next. Datacenter SIO 192.168.1.30 192.168.1.31 192.168.1.32 Information Select devices Replicate selection <table><thead><tr><th>Device Name</th><th>Free (GB)</th><th>SSD</th><th>Add Device</th><th>Create VM...</th><th>Storage Pool</th></tr></thead><tbody><tr><td>mpx.vmhba1:C0:T2:L0</td><td>105</td><td></td><td>☐</td><td>☐</td><td>SP1 (PD1) ▾</td></tr><tr><td>mpx.vmhba1:C0:T1:L0</td><td>105</td><td></td><td>☒</td><td>☒</td><td>SP1 (PD1) ▾</td></tr><tr><td>mpx.vmhba1:C0:T0:L0</td><td>33</td><td></td><td>☐</td><td>☒</td><td>SP1 (PD1) ▾</td></tr></tbody></table> Datacenter SIO 192.168.1.30 192.168.1.31 192.168.1.32 Information Select devices Replicate selection <table><thead><tr><th>Device Name</th><th>Free (GB)</th><th>SSD</th><th>Add Device</th><th>Create VM...</th><th>Storage Pool</th></tr></thead><tbody><tr><td>mpx.vmhba1:C0:T2:L0</td><td>105</td><td></td><td>☐</td><td>☐</td><td>SP1 (PD1) ▾</td></tr><tr><td>mpx.vmhba1:C0:T1:L0</td><td>105</td><td></td><td>☒</td><td>☒</td><td>SP1 (PD1) ▾</td></tr><tr><td>mpx.vmhba1:C0:T0:L0</td><td>33</td><td></td><td>☐</td><td>☒</td><td>SP1 (PD1) ▾</td></tr></tbody></table>	Device Name	Free (GB)	SSD	Add Device	Create VM...	Storage Pool	mpx.vmhba1:C0:T2:L0	105		☐	☐	SP1 (PD1) ▾	mpx.vmhba1:C0:T1:L0	105		☒	☒	SP1 (PD1) ▾	mpx.vmhba1:C0:T0:L0	33		☐	☒	SP1 (PD1) ▾	Device Name	Free (GB)	SSD	Add Device	Create VM...	Storage Pool	mpx.vmhba1:C0:T2:L0	105		☐	☐	SP1 (PD1) ▾	mpx.vmhba1:C0:T1:L0	105		☒	☒	SP1 (PD1) ▾	mpx.vmhba1:C0:T0:L0	33		☐	☒	SP1 (PD1) ▾
Device Name	Free (GB)	SSD	Add Device	Create VM...	Storage Pool																																												
mpx.vmhba1:C0:T2:L0	105		☐	☐	SP1 (PD1) ▾																																												
mpx.vmhba1:C0:T1:L0	105		☒	☒	SP1 (PD1) ▾																																												
mpx.vmhba1:C0:T0:L0	33		☐	☒	SP1 (PD1) ▾																																												
Device Name	Free (GB)	SSD	Add Device	Create VM...	Storage Pool																																												
mpx.vmhba1:C0:T2:L0	105		☐	☐	SP1 (PD1) ▾																																												
mpx.vmhba1:C0:T1:L0	105		☒	☒	SP1 (PD1) ▾																																												
mpx.vmhba1:C0:T0:L0	33		☐	☒	SP1 (PD1) ▾																																												

Step	Action																								
15.	On the Add SDC screen, select all three hosts (or select a parent object), enter P@ssw0rd as the password for all (click Show passwords to make sure it is typed correctly). Do NOT click Next. Select ESXs to add as SDCs to ScaleIO system: Select ESXs to add as SDCs: <table><thead><tr><th>Cluster/ESX</th><th>SDC</th><th>ESX Root Password</th><th>SDC mode</th></tr></thead><tbody><tr><td>▼ Datacenter</td><td>☒</td><td>P@ssw0rd</td><td>ESX</td></tr><tr><td>▼ SIO</td><td>☒</td><td>P@ssw0rd</td><td>ESX</td></tr><tr><td> 192.168.1.30</td><td>☒</td><td>P@ssw0rd</td><td>ESX</td></tr><tr><td> 192.168.1.31</td><td>☒</td><td>P@ssw0rd</td><td>ESX</td></tr><tr><td> 192.168.1.32</td><td>☒</td><td>P@ssw0rd</td><td>ESX</td></tr></tbody></table> ☒ Show passwords	Cluster/ESX	SDC	ESX Root Password	SDC mode	▼ Datacenter	☒	P@ssw0rd	ESX	▼ SIO	☒	P@ssw0rd	ESX	192.168.1.30	☒	P@ssw0rd	ESX	192.168.1.31	☒	P@ssw0rd	ESX	192.168.1.32	☒	P@ssw0rd	ESX
Cluster/ESX	SDC	ESX Root Password	SDC mode																						
▼ Datacenter	☒	P@ssw0rd	ESX																						
▼ SIO	☒	P@ssw0rd	ESX																						
192.168.1.30	☒	P@ssw0rd	ESX																						
192.168.1.31	☒	P@ssw0rd	ESX																						
192.168.1.32	☒	P@ssw0rd	ESX																						
16.	On the same screen, click Disable for Enable/Disable SCSI LUN number comparison... Click OK on the popup, then click Next. Enable/Disable SCSI LUN number comparison for hosts: Enable Note: to install ScaleIO VIB, hosts acceptance level will be re Enable Disable Warning This configuration defines whether VMFS considers the LUN number when it compares the LUN to the value found in the VMFS volume metadata. Disabling LUN number comparison will disable consideration of the LUN number when the metadata is compared to what is returned from the discovery of a given LUN by an ESX host. Only the disk serial number will be compared to determine if a mismatch exists. OK																								



Step	Action
17.	On the Configure Upgrade Components screen, select 192.168. as the host for the Gateway VM, enter P@ssw0rd as the password for the gateway, enter P@ssw0rd as the password for LIA, then click Next. ScaleIO Gateway configuration: The ScaleIO Gateway is used to collect logs and upgrade ScaleIO components. Select an ESX host for the ScaleIO Gateway virtual machine: 192.168.1.30 Enter a password for the Gateway admin user: ***** Confirm the password ***** LIA Configuration The LIA is installed on the SVMs to enable communication with the ScaleIO Gateway. The LIA password must be the same across all ScaleIO components in the same ScaleIO sys Enter a password ***** Confirm the password *****



Step	Action
18.	On the Select OVA template screen, choose the previously uploaded template, enter P@ssw0rd as the root password, and click Next Select an existing template for the ScaleIO virtual machines (SVM):  Select an existing template for the ScaleIO virtual machines (SVM): 
19.	On the Configure networks screen, select the VM Network for the Management network. For the Data network, click Create new network Select networks that will be used on ScaleIO VMs: 

Step	Action																
20.	For the values for the new network, enter what is shown below, then click OK Network name: SIO-Storage VMkernel name: SIO-Storage-vmk VLAN ID: 0 <table><thead><tr><th>ESX Name</th><th>Data NIC</th><th>VMkernel IP</th><th>VMkernel Subnet Mask</th></tr></thead><tbody><tr><td>192.168.1.30</td><td>vmnic1 (10000MB/s) (...)</td><td>192.168.2.30</td><td>255.255.255.0</td></tr><tr><td>192.168.1.31</td><td>vmnic1 (10000MB/s) (...)</td><td>192.168.2.31</td><td>255.255.255.0</td></tr><tr><td>192.168.1.32</td><td>vmnic1 (10000MB/s) (...)</td><td>192.168.2.32</td><td>255.255.255.0</td></tr></tbody></table>	ESX Name	Data NIC	VMkernel IP	VMkernel Subnet Mask	192.168.1.30	vmnic1 (10000MB/s) (...)	192.168.2.30	255.255.255.0	192.168.1.31	vmnic1 (10000MB/s) (...)	192.168.2.31	255.255.255.0	192.168.1.32	vmnic1 (10000MB/s) (...)	192.168.2.32	255.255.255.0
ESX Name	Data NIC	VMkernel IP	VMkernel Subnet Mask														
192.168.1.30	vmnic1 (10000MB/s) (...)	192.168.2.30	255.255.255.0														
192.168.1.31	vmnic1 (10000MB/s) (...)	192.168.2.31	255.255.255.0														
192.168.1.32	vmnic1 (10000MB/s) (...)	192.168.2.32	255.255.255.0														
21.	The network configuration will take place. When it is finished configuring the networks, click Close on the progress popup, and close on the Create New Data Network window, to return to the Configure networks screen. Command progress Please wait, the network is being configured across all the selected ESX hosts View details... The network was successfully configured on all the ESX hosts. Close View progress OK Close																

Step	Action																																								
22.	Wait a moment for the new SIO-Storage network to appear as the Data network. Then click Next. Management network label: VM Network Data network label: SIO-Storage Create new network																																								
23.	On the Configure SVM Screen, enter the values as shown below (scroll from left to right to access the different values), and then click Next. <table><thead><tr><th>ESX Name</th><th>Mgmt IP</th><th>Mgmt Subnet Mask</th><th>Default Gateway</th></tr></thead><tbody><tr><td>192.168.1.30 (ScaleIO Gateway) </td><td>192.168.1.39</td><td>255.255.255.0</td><td>192.168.1.1</td></tr><tr><td>192.168.1.30 (Primary MDM) </td><td>192.168.1.40</td><td>255.255.255.0</td><td>192.168.1.1</td></tr><tr><td>192.168.1.31 (Secondary MDM) </td><td>192.168.1.41</td><td>255.255.255.0</td><td>192.168.1.1</td></tr><tr><td>192.168.1.32 (Tie Breaker) </td><td>192.168.1.42</td><td>255.255.255.0</td><td>192.168.1.1</td></tr></tbody></table> <table><thead><tr><th>ESX Name</th><th>Data IP</th><th>Data Subnet Mask</th><th>Datastore</th></tr></thead><tbody><tr><td>192.168.1.30 (ScaleIO Gateway) </td><td>192.168.2.39</td><td>255.255.255.0</td><td>Automatic v </td></tr><tr><td>192.168.1.30 (Primary MDM) </td><td>192.168.2.40</td><td>255.255.255.0</td><td>Automatic v </td></tr><tr><td>192.168.1.31 (Secondary MDM) </td><td>192.168.2.41</td><td>255.255.255.0</td><td>Automatic v </td></tr><tr><td>192.168.1.32 (Tie Breaker) </td><td>192.168.2.42</td><td>255.255.255.0</td><td>Automatic v </td></tr></tbody></table>	ESX Name	Mgmt IP	Mgmt Subnet Mask	Default Gateway	192.168.1.30 (ScaleIO Gateway) 	192.168.1.39	255.255.255.0	192.168.1.1	192.168.1.30 (Primary MDM) 	192.168.1.40	255.255.255.0	192.168.1.1	192.168.1.31 (Secondary MDM) 	192.168.1.41	255.255.255.0	192.168.1.1	192.168.1.32 (Tie Breaker) 	192.168.1.42	255.255.255.0	192.168.1.1	ESX Name	Data IP	Data Subnet Mask	Datastore	192.168.1.30 (ScaleIO Gateway) 	192.168.2.39	255.255.255.0	Automatic v	192.168.1.30 (Primary MDM) 	192.168.2.40	255.255.255.0	Automatic v	192.168.1.31 (Secondary MDM) 	192.168.2.41	255.255.255.0	Automatic v	192.168.1.32 (Tie Breaker) 	192.168.2.42	255.255.255.0	Automatic v
ESX Name	Mgmt IP	Mgmt Subnet Mask	Default Gateway																																						
192.168.1.30 (ScaleIO Gateway) 	192.168.1.39	255.255.255.0	192.168.1.1																																						
192.168.1.30 (Primary MDM) 	192.168.1.40	255.255.255.0	192.168.1.1																																						
192.168.1.31 (Secondary MDM) 	192.168.1.41	255.255.255.0	192.168.1.1																																						
192.168.1.32 (Tie Breaker) 	192.168.1.42	255.255.255.0	192.168.1.1																																						
ESX Name	Data IP	Data Subnet Mask	Datastore																																						
192.168.1.30 (ScaleIO Gateway) 	192.168.2.39	255.255.255.0	Automatic v																																						
192.168.1.30 (Primary MDM) 	192.168.2.40	255.255.255.0	Automatic v																																						
192.168.1.31 (Secondary MDM) 	192.168.2.41	255.255.255.0	Automatic v																																						
192.168.1.32 (Tie Breaker) 	192.168.2.42	255.255.255.0	Automatic v																																						

Step	Action														
24.	Review the configuration summary, click Finish. Please review configuration summary before installation begins: <table> <tr><td>Number of SDSs:</td><td>3</td></tr> <tr><td>Number of SDCs:</td><td>3</td></tr> <tr><td>Number of ESXs:</td><td>3</td></tr> <tr><td>Number of physical devices:</td><td>3</td></tr> <tr><td>Number of Protection Domains:</td><td>1</td></tr> <tr><td>Number of Storage Pools:</td><td>1</td></tr> <tr><td>Total capacity (GB):</td><td>315.00</td></tr> </table> Click Finish to begin deployment or Back to make changes.	Number of SDSs:	3	Number of SDCs:	3	Number of ESXs:	3	Number of physical devices:	3	Number of Protection Domains:	1	Number of Storage Pools:	1	Total capacity (GB):	315.00
Number of SDSs:	3														
Number of SDCs:	3														
Number of ESXs:	3														
Number of physical devices:	3														
Number of Protection Domains:	1														
Number of Storage Pools:	1														
Total capacity (GB):	315.00														
25.	On the authorization popup, enter root P@ssw0rd, and click OK. vCenter Authorization ✕ vCenter authentication required  Enter user name and password to connect to vCenter vCenter: User name: root Password: ***** OK Cancel														

Step	Action
26.	The installation will begin. It may take up to 45 minutes to complete. It is common in our environment to experience errors. If you see an Error, click Pause (then Yes to confirm), wait for it to stop the Deployment, click Continue the deployment (Yes to confirm)   
27.	Do not be concerned with errors regarding Datastore usage. This is due to “VMDK Creation” which creates a single VMDK on each disk, consuming nearly the whole disk. 


Step	Action
28.	Also, these errors are expected and can be ignored 
29.	When it finally completes without errors, click Finish 




Step	Action																																
30.	The lower-left of the vSphere screen should look like this after a successful deployment. ▼ EMC ScaleIO <table><tr><td></td><td>ScaleIO Systems</td><td>1</td><td>></td></tr><tr><td></td><td>Protection Domains</td><td>1</td><td>></td></tr><tr><td></td><td>Storage Pools</td><td>1</td><td>></td></tr><tr><td></td><td>SDSs</td><td>3</td><td>></td></tr><tr><td></td><td>SDCs</td><td>3</td><td>></td></tr><tr><td></td><td>Volumes</td><td>0</td><td>></td></tr><tr><td></td><td>Devices</td><td>3</td><td>></td></tr><tr><td></td><td>Fault Sets</td><td>0</td><td>></td></tr></table>		ScaleIO Systems	1	>		Protection Domains	1	>		Storage Pools	1	>		SDSs	3	>		SDCs	3	>		Volumes	0	>		Devices	3	>		Fault Sets	0	>
	ScaleIO Systems	1	>																														
	Protection Domains	1	>																														
	Storage Pools	1	>																														
	SDSs	3	>																														
	SDCs	3	>																														
	Volumes	0	>																														
	Devices	3	>																														
	Fault Sets	0	>																														

Lab Exercise 3-A: ScaleIO Configuration and Management



Purpose:	Perform basic configuration, management and monitoring of a ScaleIO cluster in a physical Linux/Windows environment.
Tasks:	✓ Practice using the ScaleIO GUI to perform the supported configuration, management and monitoring operations ✓ Gain familiarity with the ScaleIO CLI syntax by using it to exercise typical day-to-day tasks such as provisioning and storage management
References:	ScaleIO Lab Diagram (graphically showing relevant details for all VMs within a student pod – refer to Page 2)

Lab 3-A: Task 1 – GUI Introduction


Step	Action
	This task has you taking a quick look at the ScaleIO GUI. It is available for Linux and Windows. You will install it on the Windows DC, and take a quick look at the dashboard and backend views.
1.	From the “dc” workstation, open an explorer window to c:\share\sw\GUI_for_Windows. Launch the msi installer 

Step	Action
2.	Accept all the default settings and Finish 
3.	Launch the GUI under Start → Programs → ScaleIO 
4.	Log on to Inx-1 as User: admin Password: P@ssw0rd 

Step	Action																								
5.	Take a close look at the Dashboard The screenshot shows the 'System Overview' dashboard. At the top, there are tabs for 'Dashboard', 'Backend', and 'Alerts'. The 'Dashboard' tab is active. The main content area is divided into several sections: Capacity: A donut chart showing 'Total 416.0 GB'. The chart is divided into two segments: a blue segment representing '141.4 GB' and a grey segment representing '274.6 GB'. A red arrow points to the grey segment with the text 'no usable capacity'. I/O Workload: Shows '0.0 KB/s' and '0 IOPS'. A red arrow points to the '0.0 KB/s' value with the text 'Nothing happening'. Rebalance: Shows '0.0 KB/s' and '0.0 KB left'. Rebuild: Shows '0.0 KB/s' and '0.0 KB left'. SDCs: Shows '3' defined SDCs. Volumes: Shows '0 Mapped' volumes. Protection Domains: Shows '1' protection domain. SDSs: Shows '4' devices. Management: Shows 'Clustered' status. At the bottom, there is a table with the following data: <table><tr><th>Item</th><th>Total Capacity</th><th>Capacity In-Use</th><th>I/O</th><th>Bandwidth</th><th>IOPS</th><th>Rebuild</th><th>Rebalance</th></tr><tr><td>System</td><td>416.0 GB</td><td>0.0 KB (0.0 %)</td><td>0.0 KB/s</td><td>0</td><td>0.0 KB/s</td><td>0.0 KB/s</td><td>0.0 KB/s</td></tr><tr><td>default</td><td></td><td></td><td></td><td></td><td></td><td>0.0 KB/s</td><td>0.0 KB/s</td></tr></table>	Item	Total Capacity	Capacity In-Use	I/O	Bandwidth	IOPS	Rebuild	Rebalance	System	416.0 GB	0.0 KB (0.0 %)	0.0 KB/s	0	0.0 KB/s	0.0 KB/s	0.0 KB/s	default						0.0 KB/s	0.0 KB/s
Item	Total Capacity	Capacity In-Use	I/O	Bandwidth	IOPS	Rebuild	Rebalance																		
System	416.0 GB	0.0 KB (0.0 %)	0.0 KB/s	0	0.0 KB/s	0.0 KB/s	0.0 KB/s																		
default						0.0 KB/s	0.0 KB/s																		
6.	Click on Backend to take a close look at the backend view The screenshot shows the 'Backend' view. At the top, there are tabs for 'Overview', 'Dashboard', 'Backend', and 'Alerts'. The 'Backend' tab is active. The main content area is a table with the following data: <table><tr><th>Item</th><th>Total Capacity</th><th>Capacity In-Use</th><th>I/O</th><th>Bandwidth</th><th>IOPS</th><th>Rebuild</th><th>Rebalance</th></tr><tr><td>System</td><td>416.0 GB</td><td>0.0 KB (0.0 %)</td><td>0.0 KB/s</td><td>0</td><td>0.0 KB/s</td><td>0.0 KB/s</td><td>0.0 KB/s</td></tr><tr><td>default</td><td></td><td></td><td></td><td></td><td></td><td>0.0 KB/s</td><td>0.0 KB/s</td></tr></table>	Item	Total Capacity	Capacity In-Use	I/O	Bandwidth	IOPS	Rebuild	Rebalance	System	416.0 GB	0.0 KB (0.0 %)	0.0 KB/s	0	0.0 KB/s	0.0 KB/s	0.0 KB/s	default						0.0 KB/s	0.0 KB/s
Item	Total Capacity	Capacity In-Use	I/O	Bandwidth	IOPS	Rebuild	Rebalance																		
System	416.0 GB	0.0 KB (0.0 %)	0.0 KB/s	0	0.0 KB/s	0.0 KB/s	0.0 KB/s																		
default						0.0 KB/s	0.0 KB/s																		

Step	Action																																				
7.	The default view is By SDS. Take a look at the SDS's in the protection domain by expanding the “default” protection domain 																																				
8.	In the upper-right of the interface, switch from By SDS, to By Storage Pools. 																																				
9.	Expand the tree on left to view all the components comprising the current default storage pool  <table><thead><tr><th>Item</th><th>Total Capacity</th><th>Capacity In-Use</th></tr></thead><tbody><tr><td>System</td><td>416.0 GB</td><td>0.0 KB (0.0 %)</td></tr><tr><td>default</td><td>416.0 GB</td><td>0.0 KB (0.0 %)</td></tr><tr><td>default</td><td>416.0 GB</td><td>0.0 KB (0.0 %)</td></tr><tr><td>SDS_[192.168.1.10]</td><td></td><td></td></tr><tr><td>/dev/sdb</td><td>104.0 GB</td><td>0.0 KB (0.0 %)</td></tr><tr><td>SDS_[192.168.1.11]</td><td></td><td></td></tr><tr><td>/dev/sdb</td><td>104.0 GB</td><td>0.0 KB (0.0 %)</td></tr><tr><td>SDS_[192.168.1.12]</td><td></td><td></td></tr><tr><td>/dev/sdb</td><td>104.0 GB</td><td>0.0 KB (0.0 %)</td></tr><tr><td>SDSWin2</td><td></td><td></td></tr><tr><td>E</td><td>104.0 GB</td><td>0.0 KB (0.0 %)</td></tr></tbody></table>	Item	Total Capacity	Capacity In-Use	System	416.0 GB	0.0 KB (0.0 %)	default	416.0 GB	0.0 KB (0.0 %)	default	416.0 GB	0.0 KB (0.0 %)	SDS_[192.168.1.10]			/dev/sdb	104.0 GB	0.0 KB (0.0 %)	SDS_[192.168.1.11]			/dev/sdb	104.0 GB	0.0 KB (0.0 %)	SDS_[192.168.1.12]			/dev/sdb	104.0 GB	0.0 KB (0.0 %)	SDSWin2			E	104.0 GB	0.0 KB (0.0 %)
Item	Total Capacity	Capacity In-Use																																			
System	416.0 GB	0.0 KB (0.0 %)																																			
default	416.0 GB	0.0 KB (0.0 %)																																			
default	416.0 GB	0.0 KB (0.0 %)																																			
SDS_[192.168.1.10]																																					
/dev/sdb	104.0 GB	0.0 KB (0.0 %)																																			
SDS_[192.168.1.11]																																					
/dev/sdb	104.0 GB	0.0 KB (0.0 %)																																			
SDS_[192.168.1.12]																																					
/dev/sdb	104.0 GB	0.0 KB (0.0 %)																																			
SDSWin2																																					
E	104.0 GB	0.0 KB (0.0 %)																																			

Lab 3-A: Task 2 – SCLI

Step	Action
	Here you will run scli commands to gather basic information.
1.	Minimize the GUI, and launch a putty session with lnx-1, by clicking on the desktop icon (will log you in as root)  <pre>Using username "root". Last login: Thu Jul 30 10:36:45 2015 from 192.168.1.50 [root@Lnx-1 ~]#</pre>
2.	Run the following command to display basic help information on scli <pre>[root@Lnx-1 ~]# scli Usage: scli --help [Options] Description: Display help about one or all types of commands Parameters: Options: CHOOSE ONE --mdm Display help about commands relating to the MDM --sds Display help about commands relating to the SDS --vol Display help about commands relating to volumes --sdc Display help about commands relating to SDC --SCSI Display help about commands relating to SCSI --general Display help about general commands, e.g. licen on, etc. --user Users login and management --all Display help about all commands</pre>
3.	Run the following command to gain privileged access to the ScaleIO cluster scli --login --username admin --password P@ssw0rd <pre>[root@Lnx-1 ~]# scli --login --username admin --password P@ssw0rd Logged in. User role is Administrator. System ID is 4b36f8677d4ecb5d [root@Lnx-1 ~]#</pre> <i>Note: if you omit the "--password" switch, it will prompt for secure password entry.</i>

Step	Action
4.	Enter the following command to retrieve lots of information from the cluster <pre>scli -query_all</pre> <pre>[root@LnX-1 ~]# scli --query_all</pre> The output will quickly scroll past the screen
5.	To retrieve the information one screen at a time, enter the following command: <pre>scli -query_all less</pre> <pre>[root@LnX-1 ~]# scli --query_all less</pre>
6.	It will output information just one screen at a time. Hit [spacebar] to continue to the next page and q to exit the command. <pre>System Info: Product: EMC ScaleIO Version: R1_32.403.2 ID: 4b36f8677d4ecb5d Manager ID: 000000000000000000 License info: Installation ID: 370409a270d6e920 SWID: Maximum capacity: Unlimited Usage time left: Unlimited *** Non-Production License *** Enterprise features: Enabled The system was activated 1 days ago</pre>
7.	Enter the following command to identify the protection domain. <pre>scli --query_all grep Protection</pre> <pre>[root@LnX-1 ~]# scli --query_all grep Protection Query all returned 1 Protection Domain: Protection Domain default (Id: 18cafc9300000000) has 1 storage pools, 0 Fault Sets, 4 SDS nodes, 0 volumes and 128.0 GB (131072 MB) available for volume allocation</pre>


Step	Action
8.	Enter the following command for detailed information on the protection domain “default”. (You can either scroll through the results or add “ less” to the command to view one page at a time. Take a moment to review the output. <pre>scli --query_protection_domain --protection_domain_name default</pre> <pre>[root@LnX-1 ~]# scli --query_protection_domain --protection_domain_name default</pre>
9.	Enter the following command to identify the protection domain. <pre>scli --query_all grep Storage</pre> <pre>[root@LnX-1 ~]# scli --query_all grep Storage Storage Pool default {Id: a6041e4d00000000} has 0 volumes and 128.0 GB {131072 MB} ume allocation [root@LnX-1 ~]#</pre>
10.	Enter the following command (on a single line) for detailed information on the Storage Pool “default”. (You can either scroll through the results or add “ less” to the command to view one page at a time. Take a moment to review the output. <pre>scli --query_storage_pool --protection_domain_name default --storage_pool_name default</pre> <pre>[root@LnX-1 ~]# scli --query_storage_pool --protection_domain_name default --storage_pool_name default</pre>
11.	Run the following command to list your SDSs: <pre>scli --query_all_sds</pre> <pre>Query-all-SDS returned 4 SDS nodes. Protection Domain 18cafc9300000000 Name: default SDS ID: b8d54f6d00000004 Name: SDSWin2 State: Connected, Joined IP: 192.168.1.21 Port: 7072 SDS ID: b8d5285f00000002 Name: SDS_[192.168.1.11] State: Connected, Joined IP: 192.168.1.11 Port: 7072 SDS ID: b8d5285e00000001 Name: SDS_[192.168.1.12] State: Connected, Joined IP: 192.168.1.12 Port: 7072 SDS ID: b8d5285d00000000 Name: SDS_[192.168.1.10] State: Connected, Joined IP: 192.168.1.10 Port: 7072 [root@LnX-1 ~]#</pre>


Step	Action
12.	Query one of your SDSs, using its ID and carefully examine the output: <pre>scli --query_sds --sds_id <SDS ID></pre> <pre>SDS ID: b8d54f6d00000004 Name: SDSWin2 State: Connected, Jo SDS ID: b8d5285f00000002 Name: SDS_[192.168.1.11] State: Co 72 SDS ID: b8d5285e00000001 Name: SDS_[192.168.1.12] State: Co 72 SDS ID: b8d5285d00000000 Name: SDS_[192.168.1.10] State: Co 72 [root@Lnx-1 ~]# scli --query_sds --sds_id b8d54f6d00000004</pre> Look for information like, Path: and total and unused capacity.
13.	Run this command to list your SDCs: <pre>scli --query_all_sdc</pre> Example output: <pre>[root@Lnx-1 ~]# scli --query_all_sdc MDM restricted SDC mode: Disabled Query all SDC returned 3 SDC nodes. SDC ID: c842438d00000000 Name: N/A IP: 192.168.1.10 EACBA3939F1 Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second SDC ID: c842438e00000001 Name: N/A IP: 192.168.1.12 D6A4CB38FAF Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second SDC ID: c842438f00000002 Name: N/A IP: 192.168.1.11 EDE4BA577F3 Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second</pre>


Step	Action
14.	All three of the SDCs still have the name given to them by the Installation Manager during their creation. Name them to reflect their purpose and host names. <pre>scli --rename_sdc --sdc_id <SDC ID> --new_name SDC_Lnx1</pre> (pick the SDC ID corresponding to the IP 192.168.1.10) <pre>scli --rename_sdc --sdc_id <SDC ID> --new_name SDC_Lnx2</pre> (pick the SDC ID corresponding to the IP 192.168.1.11) <pre>scli --rename_sdc --sdc_id <SDC ID> --new_name SDC_Lnx3</pre> (pick the SDC ID corresponding to the IP 192.168.1.12) <pre>[root@LnX-1 ~]# scli --rename_sdc --sdc_id c842438d00000000 --new_name SDC_Lnx1 Successfully renamed sdc with ID c842438d00000000 to SDC_Lnx1 [root@LnX-1 ~]# scli --rename_sdc --sdc_id c842438d00000002 --new_name SDC_Lnx2 Error: MDM failed command. Status: Could not find the SDC [root@LnX-1 ~]# scli --rename_sdc --sdc_id c842438f00000002 --new_name SDC_Lnx2 Successfully renamed sdc with ID c842438f00000002 to SDC_Lnx2 [root@LnX-1 ~]# scli --rename_sdc --sdc_id c842438e00000001 --new_name SDC_Lnx3 Successfully renamed sdc with ID c842438e00000001 to SDC_Lnx3</pre>
15.	Rerun <code>scli --query_all_sdc</code> and ensure the new names are in effect: <pre>[root@LnX-1 ~]# scli --query_all_sdc MDM restricted SDC mode: Disabled Query all SDC returned 3 SDC nodes. SDC ID: c842438d00000000 Name: SDC_Lnx1 IP: 192.168.1.10 214-0EACBA3939F1 Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second SDC ID: c842438e00000001 Name: SDC_Lnx3 IP: 192.168.1.12 B0E-5D6A4CB38FAE Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second SDC ID: c842438f00000002 Name: SDC_Lnx2 IP: 192.168.1.11 94C-6EDE4BA577F3 Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second</pre>

Lab 3-A: Task 3 – Create volumes

Step	Action
------	--------

Step	Action
	You will create volumes via scli.
1.	At the command prompt on Lnx-1, enter (all one command): <pre>scli --add_volume --protection_domain_name default --storage_pool_name default --thin_provisioned --volume_name voll --size_gb 12</pre> <pre>[root@Lnx-1 ~]# scli --add_volume --protection_domain_name default --storage_pool_name default --thin_provisioned --volume_name voll --size_gb 12 Warning: Rounding up the volume size to 16 GB Successfully created volume of size 16 GB. Object ID b8fb1c3900000000 [root@Lnx-1 ~]#</pre> Note: ScaleIO rounded up the provisioned capacity to 16 GB. Due to the nature of ScaleIO's mesh mirroring, it works best in units of 8 GB.
2.	List all the volumes and look for the volume you just created. <pre>scli --query_all_volumes</pre> <pre>[root@Lnx-1 ~]# scli --query_all_volumes Query-all-volumes returned 1 volumes Protection Domain 18cafc9300000000 Name: default Storage Pool a6041e4d00000000 Name: default Volume ID: b8fb1c3900000000 Name: voll Size: 16.0 GB (16384 MB) Unmapped Thin-provisioned</pre>
3.	Minimize the Putty session and bring up the ScaleIO GUI.
4.	On Dashboard→System Overview, look for the Volumes tile. You should see 1 volume defined.  Volumes 0 Mapped Defined: 1 Free: 112.0 GB

Step	Action
5.	Now look for the Capacity tile. Notice, however, that it doesn't show any storage as being used (Protected) yet.  Why? _____
6.	Create a new thin-provisioned volume of 16 GB named vol 2. <pre>scli --add_volume --protection_domain_name default --storage_pool_name default --thin_provisioned --volume_name vol2 --size_gb 16</pre> <pre>[root@Lnx-1 ~]# scli --add_volume --protection_domain_name default --storage_pool_name default --thin_provisioned --volume_name vol2 --size_gb 16</pre> Refer back to the GUI. Any change on the Capacity circle yet? _____
7.	Now create two more <u>thick-provisioned</u> volumes, vol3 and vol4. Note: Thick provisioning is the default. Notice the lack of the --thin_provisioned qualifier in the commands. <pre>scli --add_volume --protection_domain_name default --storage_pool_name default --volume_name vol3 --size_gb 16</pre> <pre>scli --add_volume --protection_domain_name default --storage_pool_name default --volume_name vol4 --size_gb 16</pre> <pre>[root@Lnx-1 ~]# scli --add_volume --protection_domain_name default --storage_pool_name default --volume_name vol3 --size_gb 16 Successfully created volume of size 16 GB. Object ID b8fb1c3b00000002 [root@Lnx-1 ~]# scli --add_volume --protection_domain_name default --storage_pool_name default --volume_name vol4 --size_gb 16 Successfully created volume of size 16 GB. Object ID b8fb1c3c00000003</pre>

Step	Action
8.	Check the Capacity circle.  You created two 16GB thick-provisioned devices, for a total of 32GB usable capacity. Why does ScaleIO show 64GB of protected storage?

Lab 3-A: Task 4 – Map Volumes to SDC


Step	Action
	You will provision created volumes to an sdc host. Then, from the host, you will run the commands to access the volume.
1.	Note: This task assumes that Lnx-1 has ownership of the Primary MDM. On Lnx-1, run the following command to map vol1 to Lnx-1: <pre>scli --map_volume_to_sdc --volume_name vol1 --sdc_name SDC_Lnx1</pre> <pre>[root@Lnx-1 ~]# scli --map_volume_to_sdc --volume_name vol1 --sdc_name SDC_Lnx1 Successfully mapped volume vol1 to SDC SDC_Lnx1 [root@Lnx-1 ~]#</pre>

Step	Action
2.	Still on Lnx-1, (the Primary MDM) map vol2 to Lnx-2 and vol3 to Lnx-3. <pre data-bbox="217 300 1463 451">[root@Lnx-1 ~]# scli --map_volume_to_sdc --volume_name vol2 --sdc_name SDC_Lnx2 Successfully mapped volume vol2 to SDC SDC_Lnx2 [root@Lnx-1 ~]# scli --map_volume_to_sdc --volume_name vol3 --sdc_name SDC_Lnx3 Successfully mapped volume vol3 to SDC SDC_Lnx3 [root@Lnx-1 ~]# █</pre>
3.	Note: At this point, we are running commands on Lnx-1, Lnx-2 and Lnx-3 in their role as SDCs. On Lnx-1, run the <code>fdisk -l</code> command and look for a ScaleIO device. It should appear as <code>/dev/scinia</code>: <pre data-bbox="217 720 1360 1018">Disk /dev/scinia: 17.2 GB, 17179869184 bytes 64 heads, 32 sectors/track, 16384 cylinders Units = cylinders of 2048 * 512 = 1048576 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes Disk identifier: 0x00000000 Disk /dev/scinia doesn't contain a valid partition table</pre>

Step	Action
4.	Run the following command to prepare the device for mounting: <pre>fdisk /dev/scinia</pre> Choose (n)ew, (p)rimary partition, number 1, accept the defaults for first and last cylinders, and (w)rite it to disk. <pre> [root@LnX-1 ~]# fdisk /dev/scinia Device contains neither a valid DOS partition table, nor Sun, SGI or OSF disklabel Building a new DOS disklabel with disk identifier 0x1a42340d. Changes will remain in memory only, until you decide to write them. After that, of course, the previous content won't be recoverable. Warning: invalid flag 0x0000 of partition table 4 will be corrected by w(rite) WARNING: DOS-compatible mode is deprecated. It's strongly recommended to switch off the mode (command 'c') and change display units to sectors (command 'u'). Command (m for help): n Command action e extended p primary partition (1-4) p Partition number (1-4): 1 First cylinder (1-16384, default 1): <Enter> Using default value 1 Last cylinder, +cylinders or +size{K,M,G} (1-16384, default 16384): <Enter> Using default value 16384 Command (m for help): w The partition table has been altered! Calling ioctl() to re-read partition table. Syncing disks. </pre>


Step	Action
5.	Format the partition: <pre>mkfs.ext4 /dev/scinia</pre> <pre>[root@LnX-1 ~]# mkfs.ext4 /dev/scinia mke2fs 1.41.12 (17-May-2010) Filesystem label= OS type: Linux Block size=4096 (log=2) Fragment size=4096 (log=2) Stride=0 blocks, Stripe width=0 blocks 1048576 inodes, 4194304 blocks 209715 blocks (5.00%) reserved for the super user First data block=0 Maximum filesystem blocks=4294967296 128 block groups 32768 blocks per group, 32768 fragments per group 8192 inodes per group Superblock backups stored on blocks: 32768, 98304, 163840, 229376, 294912, 819200, 884736, 1605632, 2654208, 4096000 Writing inode tables: done Creating journal (32768 blocks): done Writing superblocks and filesystem accounting information: done This filesystem will be automatically checked every 24 mounts or 180 days, whichever comes first. Use tune2fs -c or -i to override. [root@LnX-1 ~]#</pre>
6.	Notice that the amount of “Provisioned” storage just increased slightly, from 64 to 64.8GB. The act of formatting involves writing some directories or tables to the disk device. LnX-1 has a thin provisioned disk, so as data is written to previously-unused chunks of the device, ScaleIO will grow the volume to accommodate the writes.

Step	Action																														
7.	Still on Lnx-1, create a mount point and mount the new device: <pre>mkdir -p /mnt/scaleio/1</pre> <pre>mount /dev/scinia /mnt/scaleio/1</pre> Look for the new device: <pre>df -h</pre> <pre>[root@Lnx-1 ~]# <u>mkdir -p /mnt/scaleio/1</u></pre><pre>[root@Lnx-1 ~]# <u>mount /dev/scinia /mnt/scaleio/1</u></pre><pre>[root@Lnx-1 ~]# <u>df -h</u></pre><table><thead><tr><th>Filesystem</th><th>Size</th><th>Used</th><th>Avail</th><th>Use%</th><th>Mounted on</th></tr></thead><tbody><tr><td>/dev/mapper/vg_siorh62-lv_root</td><td>12G</td><td>3.4G</td><td>7.5G</td><td>32%</td><td>/</td></tr><tr><td>tmpfs</td><td>1.9G</td><td>287M</td><td>1.6G</td><td>15%</td><td>/dev/shm</td></tr><tr><td>/dev/sda1</td><td>485M</td><td>33M</td><td>427M</td><td>8%</td><td>/boot</td></tr><tr><td>/dev/scinia</td><td>16G</td><td>172M</td><td>15G</td><td>2%</td><td>/mnt/scaleio/1</td></tr></tbody></table><pre>[root@Lnx-1 ~]#</pre>	Filesystem	Size	Used	Avail	Use%	Mounted on	/dev/mapper/vg_siorh62-lv_root	12G	3.4G	7.5G	32%	/	tmpfs	1.9G	287M	1.6G	15%	/dev/shm	/dev/sda1	485M	33M	427M	8%	/boot	/dev/scinia	16G	172M	15G	2%	/mnt/scaleio/1
Filesystem	Size	Used	Avail	Use%	Mounted on																										
/dev/mapper/vg_siorh62-lv_root	12G	3.4G	7.5G	32%	/																										
tmpfs	1.9G	287M	1.6G	15%	/dev/shm																										
/dev/sda1	485M	33M	427M	8%	/boot																										
/dev/scinia	16G	172M	15G	2%	/mnt/scaleio/1																										
8.	Connect to Lnx-2 and Lnx-3 and repeat Steps 4, 5 and 7 to map, format and mount vol 2 to Lnx-2 and vol 3 to Lnx-3 respectively																														

Step	Action
9.	Recheck the dashboard in the GUI to see the change in capacity. 

Lab 3-A: Task 4 – Map Volumes to Windows SDC

Step	Action
	You will add a new Windows SDC, and map a volume for it.
1.	We now have three Linux SDCs in the ScaleIO environment. Let's add a fourth SDC - but this time, a Windows server.
2.	On the dc desktop, click on the win-2 icon to open a remote desktop connection (will automatically log on as administrator P@ssw0rd) 

Step	Action
3.	Open an explorer window to \\dc\share\sw\Windows. Double click the sdc installer. Complete the installation using default values. 
4.	Open a command prompt (Start → Command Promt) 
5.	Run the following commands to configure Win-2 as a client of our specific ScaleIO cluster: <pre>cd "C:\Program Files\EMC\ScaleIO\sdc\bin\" drv_cfg.exe --add_mdm --ip 192.168.1.10</pre> 

Step	Action
6.	Back on Lnx-1 (minimize the remote desktop connection to win-2, open putty window to lnx-1), a query to the MDM should now show the new (fourth) SDC. <pre>[root@Lnx-1 ~]# scli --query_all_sdc MDM restricted SDC mode: Disabled Query all SDC returned 4 SDC nodes. SDC ID: c842438d00000000 Name: SDC_Lnx1 IP: 192.168.1.10 214-0EACBA3939F1 Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second SDC ID: c842438e00000001 Name: SDC_Lnx3 IP: 192.168.1.12 B0E-5D6A4CB38FAF Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second SDC ID: c842438f00000002 Name: SDC_Lnx2 IP: 192.168.1.11 94C-6EDE4BA577F3 Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second SDC ID: c8426a9d00000003 Name: N/A IP: 192.168.1.21 State: Connected 786AAACE7E52 Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second</pre>
7.	While still connected to lnx-1, rename the new SDC. <pre>scli --rename_sdc --sdc_id <SCD ID from above> --new_name SDC_Win2</pre> <pre>SDC ID: c8426a9d00000003 Name: N/A IP: 192.168.1.21 State: Connected GUID: EB630786AAACE7E52 Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second [root@Lnx-1 ~]# scli --rename_sdc --sdc_id c8426a9d00000003 --new_name SDC_Win2 Successfully renamed sdc with ID c8426a9d00000003 to SDC_Win2 [root@Lnx-1 ~]#</pre>
8.	Map vol4 to SDC_Win2 <pre>scli --map_volume_to_sdc --volume_name vol4 --sdc_name SDC_Win2</pre> <pre>[root@Lnx-1 ~]# scli --map_volume_to_sdc --volume_name vol4 --sdc_name SDC_Win2 Successfully mapped volume vol4 to SDC SDC_Win2 [root@Lnx-1 ~]#</pre>

Step	Action
9.	On Win-2, open Server Manager and select Storage → Disk Management. If you get an “Initialize Disk” pop up, just cancel it. The ScaleIO disk shows up ready to be initialized and formatted. 

Lab 3-A: Task 5 – Snapshot Volumes

Step	Action
	You will create a snapshot for an existing volume, and map it from another sdc host.
1.	First you will add “data” to a volume. From lnx-1 shell, change to the mounted volume <pre>cd /mnt/scaleio/1</pre> <pre>[root@LnX-1 ~]# cd /mnt/scaleio/1</pre>
2.	Add a file to that directory. And confirm its presence. <pre>touch original</pre> <pre>ls /mnt/scaleio/1</pre> <pre>[root@LnX-1 1]# touch original [root@LnX-1 1]# ls /mnt/scaleio/1 lost+found original [root@LnX-1 1]#</pre>
3.	Type the following command to ensure that any cached writes are written to the volume <pre>sync;sync</pre> <pre>[root@LnX-1 1]# sync;sync [root@LnX-1 1]#</pre>

Step	Action
4.	Create a snapshot of the volume called "vol1_snap" <pre>scli --snapshot_volume --volume_name vol1 --snapshot_name vol1_snap</pre> <pre>[root@Lnx-1 1]# scli --snapshot_volume --volume_name vol1 --snapshot_name vol1_snap Snapshot created successfully Source volume vol1 => b8fb434d00000004 vol1_snap</pre>
5.	Map the volume to lnx-2 <pre>scli --map_volume_to_sdc --volume_name vol1_snap --sdc_ip 192.168.1.11</pre> <pre>[root@Lnx-1 1]# scli --map_volume_to_sdc --volume_name vol1_snap --sdc_ip 192.168.1.11 Successfully mapped volume vol1_snap to SDC 192.168.1.11</pre>
6.	Connect to lnx-2 and locate the volume <pre>fdisk -l</pre> <pre>Disk /dev/scinib: 17.2 GB, 17179869184 bytes 64 heads, 32 sectors/track, 16384 cylinders Units = cylinders of 2048 * 512 = 1048576 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes Disk identifier: 0x00000000 Disk /dev/scinib doesn't contain a valid partition table</pre>
7.	Mount the volume. <pre>mkdir -p /mnt/scaleio/2</pre> <pre>mount /dev/scinib /mnt/scaleio/2</pre> <pre>[root@Lnx-2 1]# mkdir -p /mnt/scaleio/2 [root@Lnx-2 1]# mount /dev/scinib /mnt/scaleio/2</pre>

Step	Action
8.	Take a look at the contents and add a new file <pre>cd /mnt/scaleio/2</pre> <pre>ls</pre> <pre>touch new-lnx-2</pre> <pre>ls</pre> <pre>[root@LnX-2 1]# cd /mnt/scaleio/2 [root@LnX-2 2]# ls lost+found original [root@LnX-2 2]# touch new-lnx-2 [root@LnX-2 2]# ls lost+found new-lnx-2 original</pre>
9.	Unmap the volume <pre>cd /</pre> <pre>Unmount /mnt/scaleio/2</pre>
10.	Return to lnx-1, unmap the snapshot volume from lnx-2, and remove the snapshot <pre>scli --unmap_volume_from_sdc --volume_name vol1_snap --sdc_name SDC_Lnx2</pre> <pre>scli --remove_volume --volume_name vol1_snap</pre> <pre>[root@LnX-1 1]# scli --unmap_volume_from_sdc --volume_name vol1_snap --sdc_name SDC_Lnx2 Volume will not be accessible to the SDC. Press 'y' to confirm.y Successfully un-mapped volume vol1_snap from SDC SDC_Lnx2 [root@LnX-1 1]# scli --remove_volume --volume_name vol1_snap Removing a volume will erase all data on this volume. Press 'y' to confirm.y Successfully removed volume 'vol1_snap'</pre>

Lab 3-A: Task 6 – Consistency Groups

Step	Action
	You will create a consistency group (a snapshot of multiple volumes created at the same instant), and mount them on another host.

Step	Action
1.	While still connected to lnx-1, change to the source volume directory, Add a new file and examine the contents of the volume <pre>cd /mnt/scaleio/1</pre> <pre>touch consistent-data</pre> <pre>ls</pre> <pre>[root@LnX-1 1]# cd /mnt/scaleio/1 [root@LnX-1 1]# touch consistent-data [root@LnX-1 1]# ls consistent-data lost+found original</pre>
2.	From lnx-2 Repeat the above step <pre>[root@LnX-2 1]# cd /mnt/scaleio/1 [root@LnX-2 1]# touch consistent-data [root@LnX-2 1]# ls consistent-data lost+found original</pre>
3.	From lnx-1 Create a consistent snapshot of lnx-1 vol1 and lnx-2 vol2, called vol1_csnap and vol2_csnap respectively: <pre>scli --snapshot_volume --volume_name vol1,vol2 --snapshot_name vol1_csnap,vol2_csnap</pre> <pre>[root@LnX-1 1]# scli --snapshot_volume --volume_name vol1,vol2 --snapshot_name vol1_csnap,vol2_csnap Snapshots on 2 volumes created successfully Consistency group ID: c359093700000002 Source volume vol1 => b8fb434e00000004 vol1_csnap Source volume vol2 => b8fb434f00000005 vol2_csnap</pre> Note the Consistency Group ID of your CG: _____

Step	Action
4.	From Inx-1 Map both consistent snapshots to Inx-3 <pre>scli --map_volume_to_sdc --volume_name voll_csnap -sdc_ip 192.168.1.12</pre> <pre>scli --map_volume_to_sdc --volume_name vol2_csnap -sdc_ip 192.168.1.12</pre> <pre>[root@Inx-1 1]# scli --map_volume_to_sdc --volume_name voll_csnap --sdc_ip 192.168.1.12 Successfully mapped volume voll_csnap to SDC 192.168.1.12 [root@Inx-1 1]# scli --map_volume_to_sdc --volume_name vol2_csnap --sdc_ip 192.168.1.12 Successfully mapped volume vol2_csnap to SDC 192.168.1.12 [root@Inx-1 1]#</pre>
5.	From Inx-3 Examine the newly mapped volumes <pre>fdisk -l</pre> <pre> Disk /dev/scinib: 17.2 GB, 17179869184 bytes 64 heads, 32 sectors/track, 16384 cylinders Units = cylinders of 2048 * 512 = 1048576 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes Disk identifier: 0x00000000 Disk /dev/scinib doesn't contain a valid partition table Disk /dev/scinic: 17.2 GB, 17179869184 bytes 64 heads, 32 sectors/track, 16384 cylinders Units = cylinders of 2048 * 512 = 1048576 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes Disk identifier: 0x00000000 </pre>

Step	Action
6.	From Lnx-3 Mount the volumes <pre>mkdir /mnt/scaleio/csnap1 mkdir /mnt/scaleio/csnap2 mount /dev/scinib /mnt/scaleio/csnap1 mount /dev/scinic /mnt/scaleio/csnap2</pre> <pre>[root@Lnx-3 /]# mkdir /mnt/scaleio/csnap1 [root@Lnx-3 /]# mkdir /mnt/scaleio/csnap2 [root@Lnx-3 /]# mount /dev/scinib /mnt/scaleio/csnap1 [root@Lnx-3 /]# mount /dev/scinic /mnt/scaleio/csnap2</pre>
7.	From Lnx-3 Confirm the contents of the volumes <pre>ls /mnt/scaleio/csnap1 ls /mnt/scaleio/csnap2</pre> <pre>[root@Lnx-3 /]# ls /mnt/scaleio/csnap1 consistent-data lost+found original [root@Lnx-3 /]# ls /mnt/scaleio/csnap2 consistent-data lost+found original</pre>
8.	From Lnx-1 Unmap the consistent snapshots <pre>scli --unmap_volume_from_sdc --volume_name voll_csnap --sdc_ip 192.168.1.12 scli --unmap_volume_from_sdc --volume_name vol2_csnap --sdc_ip 192.168.1.12</pre> <pre>[root@Lnx-1 1]# scli --unmap_volume_from_sdc --volume_name voll_csnap --sdc_ip 192.168.1.12 Volume will not be accessible to the SDC. Press 'y' to confirm.Y [root@Lnx-1 1]# scli --unmap_volume_from_sdc --volume_name voll_csnap --sdc_ip 192.168.1.12 Volume will not be accessible to the SDC. Press 'y' to confirm.Y</pre>


Step	Action
9.	From lnx-1 Remove the consistency group snapshots. First identify the consistency group ID <pre>scli --query_volume_tree --volume_name voll</pre> <pre>[root@lnx-1 1]# scli --query_volume_tree --volume_name voll VTree ID: 87e49fed00000000 Total snapshots size: 4.0 MB (4096 KB) Total capacity in use: 399.0 MB (408576 KB) >> Volume ID: b8fb1c3900000000 Name: voll Thin-provisioned Size: 16.0 GB Capacity in use: 395.0 MB (404480 KB) Trimmed capacity: 0 Bytes Storage Pool a6041e4d00000000 Name: Cap_Pool Protection Domain 18cafc9300000000 Name: Domain1 Creation time: 2015-07-30 10:41:39 Obfuscation is disabled Uses RAM Read Cache Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second Mapped SDC: SDC ID: c842438d00000000 IP: 192.168.1.10 Name: SDC_Lnx1 >> Volume ID: b8fb434e00000004 Name: voll_csnap Snapshot of voll Size: Storage Pool a6041e4d00000000 Name: Cap_Pool Protection Domain 18cafc9300000000 Name: Domain1 Creation time: 2015-08-04 10:00:15 Obfuscation is disabled Doesn't use RAM Read Cache Read bandwidth: 0 IOPS 0 Bytes per-second Write bandwidth: 0 IOPS 0 Bytes per-second Consistency Group ID: c359093700000002 Mapped SDC: SDC ID: c842438e00000001 IP: 192.168.1.12 Name: SDC_Lnx3</pre>
10.	From lnx-1 Next, remove the consistency group <pre>scli --remove_consistency_group_snapshots --consistency_group_id <cg ID></pre> <pre>[root@lnx-1 1]# scli --remove_consistency_group_snapshots --consistency_group_id c359093700000002 The command will remove a group of snapshots. Press 'y' to confirm.</pre>


Lab 3-A: Task 7 – Inactivation of a Protection Domain

Step	Action
	You will deactivate a protection domain.
1.	On Lnx-1, change to the home directory of the root account: <code>cd /root</code>
2.	Ensure that none of the file system contents are in the host file system cache. Unmount and mount the file system once: <code>umount /mnt/scaleio/1</code> <code>mount /dev/scinia /mnt/scaleio/1</code> <code>df -h</code> At this point, we can be sure that any subsequent I/O to files in this file system will need to be serviced from the ScaleIO device – the host file system cache is empty.
3.	Verify the status of the Protection Domain: <code>scli --query_protection_domain --protection_domain_name default grep state</code> Note: Use grep to limit the output. <pre>[root@Lnx-1 1]# scli --query_protection_domain --protection_domain_name default grep state Operational state is Active 4 SDS nodes have membership state 'Joined' 4 SDS nodes have connection state 'Connected' [root@Lnx-1 1]# █</pre>

Step	Action
4.	Inactivate the Protection Domain: <pre>scli --inactivate_protection_domain --protection_domain_name default</pre> <pre>[root@LnX-1 1]# scli --inactivate_protection_domain --protection_domain_name default All application IOs will not be serviced. Press 'y' to confirm that you want to proceed ? Protection Domain default is being shutdown asynchronously [root@LnX-1 1]# █</pre> Confirm that the current state of the Protection Domain is being reported as inactive, before proceeding: <pre>scli --query_protection_domain --protection_domain_name default grep state</pre> <pre>[root@LnX-1 /]# scli --query_protection_domain --protection_domain_name default grep state Operational state is Inactive 4 SDS nodes have membership state 'Joined' 4 SDS nodes have connection state 'Connected' [root@LnX-1 /]# █</pre>
5.	Check if we still have access to files on the mounted file system: <pre>df -h</pre> <pre>ls /mnt/scaleio/1</pre> Did the ls command fail with an error? Is this expected behavior? _____
6.	Activate the Protection Domain: <pre>scli --activate_protection_domain --protection_domain_name default</pre> Confirm that the current state of the Protection Domain is being reported as active, before proceeding: <pre>scli --query_protection_domain --protection_domain_name default grep state</pre>
7.	You should now have full read/write access to the file system. Verify this: <pre>df -h</pre> <pre>ls /mnt/scaleio/1</pre>



Lab 3-A: Task 8 – Rename the Protection Domain


Step	Action
	You will rename the protection domain within the GUI
1.	Back on Lnx-1, run the following command: <pre>scli --query_all grep Protection</pre> <pre>[root@Lnx-1 logs]# scli --query_all grep Protection Query all returned 1 Protection Domain: Protection Domain default (Id: d17080e900000000) has 1 storage pools, [root@Lnx-1 logs]# █</pre> What is the Protection Domain name? _____
2.	On the dc desktop, within the ScaleIO GUI, go to the Backend view.  Right-click on the Protection Domain, and select Rename.

Step	Action
3.	In the Rename Protection Domain window, change the name of the Protection Domain to Domain1 and click OK. Close when complete.  Back on Lnx-1, run the following command: <pre>scli --query_all grep Protection</pre> <pre>[root@Lnx-1 ~]# scli --query_all grep Protection Query all returned 1 Protection Domain: Protection Domain Domain1 (Id: b4ac019d00000000) has 1 storage pools, 72.0 GB (73728 MB) available for volume allocation [root@Lnx-1 ~]# █</pre> The name of the Protection Domain has changed to Domain1.

Lab 3-A: Task 9 - Rename Storage Pool



Step	Action
	You will rename the Storage Pool within the GUI
1.	Back on Lnx-1, run the following command: <pre>scli --query_all grep Pool</pre> <pre>[root@Lnx-1 ~]# scli --query_all grep Pool Storage Pool default (Id: 5ba3a08f00000000) has 4 volumes and 72.0 GB (73728 MB) [root@Lnx-1 ~]# █</pre>

Step	Action
2.	On the dc desktop, within the ScaleIO GUI, go to the Backend view. Choose the drop-down in the upper-right-hand corner, selecting By Storage Pools. 
3.	Underneath the Domain1 Protection Domain you will find the Storage Pool named “default”.  Right-click on the Storage Pool and select Rename.

Step	Action
4.	In the Rename Storage Pool window, change the name of the Storage Pool to Cap_Pool and click OK. Close when complete.  Back on Lnx-1, run the following command: <pre>scli --query_all grep Pool</pre> <pre>[root@Lnx-1 ~]# scli --query_all grep Pool Storage Pool <u>Cap Pool</u> (Id: 5ba3a08f00000000) [root@Lnx-1 ~]#</pre> The name of the Storage Pool has changed to Cap_Pool.

Lab 3-A: Task 9 - Rename Storage Pool

Step	Action
	You will rename the SDS systems within the GUI
1.	Back on Lnx-1, run the following command: <pre>scli --query_all_sds</pre> <pre>Query-all-SDS returned 4 SDS nodes. Protection Domain d17080e900000000 Name: Domain1 SDS ID: e7f5951e00000003 Name: SDSWin2 IP: 192.168.1.21 Port: 7072 SDS ID: e7f5951d00000002 Name: SDS_[192.168.1.10] IP: 192.168.1.10 Port: 7072 SDS ID: e7f5951c00000001 Name: SDS_[192.168.1.11] IP: 192.168.1.11 Port: 7072 SDS ID: e7f5951b00000000 Name: SDS_[192.168.1.12] IP: 192.168.1.12 Port: 7072</pre>



Step	Action
2.	On the Win-1 desktop, within the ScaleIO GUI, go to the Backend view.  Click on the row labeled SDS_[192.168.1.10]. Right-click and select rename.
3.	In the Rename SDS window, change the name of the SDS to SDSLnx1 and click OK. Close when complete. 
4.	Repeat the steps above, renaming SDS 192.168.1.11 to SDSLnx2 and SDS 192.168.1.12 to SDSLnx3.



End of Lab Exercise 3-A

Lab Exercise 3-B: ScaleIO Configuration and Management - ESXi Cluster

Purpose:	Perform basic configuration, management and monitoring of a ScaleIO cluster in a VMware environment.
Task:	✓ Perform operations that are supported by the ScaleIO vSphere plug-in beyond initial cluster deployment
References:	ScaleIO Lab Diagram (graphically showing relevant details for all VMs within a student pod – refer to Page 2)



Lab 3-B: Task 1 - Explore vSphere Plugin




Step	Action
	Explore the basic information available through the ScaleIO vSphere plugin.
1.	From the dc desktop, logon to the vSphere Web Client (desktop icon) as root P@ssw0rd 
2.	On the Web Client Home Screen, click on the EMC ScaleIO icon. 

Step	Action
3.	On the lower-left corner, you can find the ScaleIO WebSphere plug-in options. 
4.	Take a moment to explore the views. After clicking and viewing each, you can return to the vCenter view by clicking the vCenter link in the upper-left corner of the screen. 

Lab 3-B: Task 2 - Create and Map ScaleIO Volumes

Step	Action
	You will create volumes, and make them available to all the ESXi (SDC) hosts, within the ScaleIO plugin.


Step	Action
1.	Navigate to the Storage Pool view and highlight the SP1 Storage Pool. On the Actions drop-down menu, choose Create volume.  The screenshot shows the 'Storage Pools' interface. A table lists storage pools, with 'SP1' highlighted. An 'Actions' dropdown menu is open for 'SP1', showing options: 'Remove Storage Pool', 'Create volume' (which is highlighted), and 'Configure RAM Read Cache'.
2.	In the pop-up window that appears, enter the information to create a volume named vol_1, sized at 32 GB, Thin provisioned. Check Map Volume to ESXs and select SIO, which will automatically choose all three ESXi hosts within the ESXi cluster named SIO.  The screenshot shows the 'Create Volume' dialog box. It contains the following fields and options: Volume name: vol_1 Number of volumes to create: 1 Volume size (GB): 32 (with a note: * Must be a multiple of 8) Volume provisioning: Thin Use RAM Read Cache: ☒ Obfuscation: Disabled Map volume to ESXs: ☒ Select ESXs: - vCenter - Datacenter - SIO 192.168.1.30 192.168.1.31 192.168.1.32

Step	Action
3.	Click OK. If prompted, enter the ScaleIO admin password.  The dialog box titled "ScaleIO authentication required" contains an information icon and the text: "Provisioning a ScaleIO system requires you to enter the admin user's password." Below this is a "Password Confirmation:" label followed by a text input field containing seven asterisks. At the bottom right are "OK" and "Cancel" buttons. A mouse cursor is pointing at the "OK" button.
4.	When finished, the following will appear:  The "Create Volume" dialog box shows a green checkmark icon and the message: "The volume has been successfully created and mapped to all the ESXs." A "Close" button is visible in the top right corner. Click Close.
5.	Repeat the steps 1-4, creating vol_2, sized at 24 GB, Thick provisioned. Choose Map Volume to ESXs and select SIO, which will automatically choose all three ESXi hosts in the SIO cluster.
6.	Go to the Volumes view.  The screenshot shows the "EMC ScaleIO" navigation pane with the following items and counts: ScaleIO Systems (1), Protection Domains (1), Storage Pools (1), SDSs (3), SDCs (3), Volumes (0), Devices (3), and Fault Sets (0). The "Volumes" item is highlighted with a mouse cursor.


Step	Action									
7.	There, you should see your two newly-created volumes: Volumes Objects Actions <table><thead><tr><th>Name</th><th>Size</th><th>Volume Type</th></tr></thead><tbody><tr><td>vol_1</td><td>32.0 GB</td><td>Thin provisioned</td></tr><tr><td>vol_2</td><td>24.0 GB</td><td>Thick provisioned</td></tr></tbody></table>	Name	Size	Volume Type	vol_1	32.0 GB	Thin provisioned	vol_2	24.0 GB	Thick provisioned
Name	Size	Volume Type								
vol_1	32.0 GB	Thin provisioned								
vol_2	24.0 GB	Thick provisioned								
8.	Navigate to vCenter Home → Hosts and Clusters Home vCenter vCenter Home Inventory Trees Hosts and Clusters									
9.	Select the 192.168. host vCenter Datacenter SIO 192.168.1.30									
10.	In the right pane, click Manage → Storage → Storage Devices Getting Started Summary Monitor Manage Settings Networking Storage Alarm Definition Storage Adapters Storage Devices Storage Devices Name									

Step	Action																					
11.	Notice the two new devices (easily identified by size) Storage Devices  <table><thead><tr><th>Name</th><th>Type</th><th>Capacity</th></tr></thead><tbody><tr><td>EMC Fibre Channel Disk (eu...</td><td>disk</td><td><u>32.00...</u></td></tr><tr><td>Local VMware Disk (mpx.vm...</td><td>disk</td><td>45.00...</td></tr><tr><td>Local NECVMWar CD-ROM (...)</td><td>cdr...</td><td></td></tr><tr><td>Local VMware Disk (mpx.vm...</td><td>disk</td><td>105.0...</td></tr><tr><td>Local VMware Disk (mpx.vm...</td><td>disk</td><td>105.0...</td></tr><tr><td>eui.4bf1d7f40db4a966d9a7...</td><td>disk</td><td><u>24.00...</u></td></tr></tbody></table>	Name	Type	Capacity	EMC Fibre Channel Disk (eu...	disk	<u>32.00...</u>	Local VMware Disk (mpx.vm...	disk	45.00...	Local NECVMWar CD-ROM (...)	cdr...		Local VMware Disk (mpx.vm...	disk	105.0...	Local VMware Disk (mpx.vm...	disk	105.0...	eui.4bf1d7f40db4a966d9a7...	disk	<u>24.00...</u>
Name	Type	Capacity																				
EMC Fibre Channel Disk (eu...	disk	<u>32.00...</u>																				
Local VMware Disk (mpx.vm...	disk	45.00...																				
Local NECVMWar CD-ROM (...)	cdr...																					
Local VMware Disk (mpx.vm...	disk	105.0...																				
Local VMware Disk (mpx.vm...	disk	105.0...																				
eui.4bf1d7f40db4a966d9a7...	disk	<u>24.00...</u>																				


Lab 3-B: Task 3 - Create Datastores



Step	Action
	You will create datastores on the volume just created and mapped. This is handled through the standard vSphere Web Client.
1.	While in the same vSphere view, right-click on 192.168. and click New Datastore 




Step	Action												
4.	☒ VMFS 5 VMFS 5 enables 2+TB LUN support. ☐ VMFS 3 VMFS 3 allows the datastore to be accessed by ESX/ESXi hosts of version earlier than 5.0. Choose VMFS 5 and click Next.												
5.	On Partition Configuration, select Use all available partitions. Click Next. Datastore Details <table> <tr> <td>Partition Configuration</td><td>Use all available partitions ▼</td></tr> <tr> <td>Datastore Size</td><td> 32.00 GB</td></tr> </table>	Partition Configuration	Use all available partitions ▼	Datastore Size	32.00 GB								
Partition Configuration	Use all available partitions ▼												
Datastore Size	32.00 GB												
6.	General: <table> <tr><td>Name</td><td>DS_SIO1</td></tr> <tr><td>Type</td><td>VMFS</td></tr> <tr><td>Datastore size</td><td>32.00 GB</td></tr> </table> Device and Formatting: <table> <tr><td>Disk/LUN</td><td>EMC Fibre Channel Disk (eui.4bf1d7f40db4a866d9a7256b00000000)</td></tr> <tr><td>Partition Format</td><td>GPT</td></tr> <tr><td>VMFS Version</td><td>VMFS 5</td></tr> </table> Review and click Finish.	Name	DS_SIO1	Type	VMFS	Datastore size	32.00 GB	Disk/LUN	EMC Fibre Channel Disk (eui.4bf1d7f40db4a866d9a7256b00000000)	Partition Format	GPT	VMFS Version	VMFS 5
Name	DS_SIO1												
Type	VMFS												
Datastore size	32.00 GB												
Disk/LUN	EMC Fibre Channel Disk (eui.4bf1d7f40db4a866d9a7256b00000000)												
Partition Format	GPT												
VMFS Version	VMFS 5												
7.	Repeat these steps to create Datastore DS_SIO2, using the 24 GB iSCSI disk.												

Step	Action
8.	At this point, all three ESXi hosts should be able to see Datastore DS_SIO1 and DS_SIO2 under the Related Objects/Datastores tab.  (the error on the top datastore relates to the VMDK creation in the initial deployment – it consumes nearly all the space on the datastore – this is expected)

Lab 3-B: Task 4 - Migrate Live VM to ScaleIO Datastore

Step	Action
	Now that you have a datastore available to all ESX hosts, you can migrate any VM to that datastore. This is done in the standard vSphere Web Client.
1.	In vSphere → Hosts and Clusters, right-click on the linux-prod VM and click Power On 





Step	Action
2.	Connect to linux_prod via desktop icon  (will log on automatically as root P@ssw0rd)
3.	Examine the disk layout of the VM. See how many devices and how much space is being consumed. <pre>fdisk -l df -h</pre>  <pre>linuxprod:~ # fdisk -l Disk /dev/sda: 3221 MB, 3221225472 bytes 255 heads, 63 sectors/track, 391 cylinders, total 6291456 sectors Units = sectors of 1 * 512 = 512 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes Disk identifier: 0x0006abda Device Boot Start End Blocks Id System /dev/sda1 2048 1028095 513024 82 Linux swap /dev/sda2 * 1028096 6291455 2631680 83 Linux linuxprod:~ # df -h Filesystem Size Used Avail Use% Mounted on /dev/sda2 2.5G 1.1G 1.3G 46% / devtmpfs 940M 116K 940M 1% /dev tmpfs 940M 0 940M 0% /dev/shm</pre>
4.	Discover the current VMware datastore hosting this VM. In vSphere, select the VM. Click Summary 

Step	Action
5.	Under VM Hardware, expand the Hard Disk Section 
6.	Back on vSphere, right-click the linux_prod VM and choose Migrate. 
7.	On the resulting pop-up windows, choose Change Datastore and click Next. 


Step	Action												
8.	Select the DS_SIO1 Datastore and click Next. Select virtual disk format: Same format as source VM Storage Policy: None ⓘ The following datastores are accessible from the destination resource that you selected. Select the virtual machine configuration files and all of the virtual disks. <table><thead><tr><th>Name</th><th>Capacity</th><th>Provisioned</th><th>Free</th></tr></thead><tbody><tr><td> DS_SIO1</td><td>31.75 GB</td><td>969.00 MB</td><td>30.80 GB</td></tr><tr><td> DS_SIO2</td><td>23.75 GB</td><td>937.00 MB</td><td>22.83 GB</td></tr></tbody></table>	Name	Capacity	Provisioned	Free	DS_SIO1	31.75 GB	969.00 MB	30.80 GB	DS_SIO2	23.75 GB	937.00 MB	22.83 GB
Name	Capacity	Provisioned	Free										
DS_SIO1	31.75 GB	969.00 MB	30.80 GB										
DS_SIO2	23.75 GB	937.00 MB	22.83 GB										
9.	Review the choices displayed. If correct, click Finish. <table><tbody><tr><td>Virtual Machines</td><td>linux_prod</td></tr><tr><td>Migration Type</td><td>Change datastore</td></tr><tr><td>Datastore</td><td>[DS_SIO1]</td></tr><tr><td>Disk Storage</td><td>Same format as source</td></tr></tbody></table>	Virtual Machines	linux_prod	Migration Type	Change datastore	Datastore	[DS_SIO1]	Disk Storage	Same format as source				
Virtual Machines	linux_prod												
Migration Type	Change datastore												
Datastore	[DS_SIO1]												
Disk Storage	Same format as source												
10.	Wait for the migration to complete. We have just accomplished an online migration of a VM from a local datastore to a ScaleIO-based datastore that is accessible by all three ESX servers. ✓ Relocate virtual machine linux_prod												

Lab 3-B: Task 5 - Migrate Live VM to other host

Step	Action
	Now that the VM is hosted a datastore available to all ESX hosts, you can migrate any VM to any other ESX host that is attached to that datastore. This is done in the standard vSphere Web Client.

Step	Action
1.	On the VMware Web Client, select the linux_prod VM. Its current host should be reported as 192.168.1.32. 
2.	Right-click linux_prod and choose Migrate... 
3.	On the first pop-up, leave the default (Change Host) and click Next. 
4.	On the next screen, make sure that SIO is chosen and click Next. 

Step	Action										
5.	Choose the host 192.168. and click Next. <table border="1"> <thead> <tr> <th>Host Name</th><th>Status</th></tr> </thead> <tbody> <tr> <td> 192.168.1.30</td><td> Normal</td></tr> <tr> <td> 192.168.1.31</td><td> Normal</td></tr> <tr> <td> 192.168.1.32</td><td> Normal</td></tr> </tbody> </table>	Host Name	Status	 192.168.1.30	 Normal	 192.168.1.31	 Normal	 192.168.1.32	 Normal		
Host Name	Status										
 192.168.1.30	 Normal										
 192.168.1.31	 Normal										
 192.168.1.32	 Normal										
6.	On the next screen, accept the defaults (Reserve CPU...), and click Next. vMotion will move the virtual machine while it remains powered on. ☒ Reserve CPU for optimal vMotion performance (Recommended)  If sufficient CPU resources are not immediately available, vMotion will not be initiated. ☐ Perform with available CPU resources  If there is a lack of CPU resources, the duration of vMotion might be extended.										
7.	On the following screen, review the choices and, if correct, click Finish. <table border="1"> <tbody> <tr> <td>Virtual Machines</td><td>linux_prod</td></tr> <tr> <td>Migration Type</td><td>Change host</td></tr> <tr> <td>Resource Pool</td><td>Resources</td></tr> <tr> <td>Host</td><td>192.168.1.30</td></tr> <tr> <td>vMotion Priority</td><td>Optimal vMotion with Reserved CPU</td></tr> </tbody> </table>	Virtual Machines	linux_prod	Migration Type	Change host	Resource Pool	Resources	Host	192.168.1.30	vMotion Priority	Optimal vMotion with Reserved CPU
Virtual Machines	linux_prod										
Migration Type	Change host										
Resource Pool	Resources										
Host	192.168.1.30										
vMotion Priority	Optimal vMotion with Reserved CPU										


Step	Action
8.	Once the migration completes, check that the Summary page for prod_linux correctly shows the new host it is running on: 192.168. .  Relocate virtual machine  linux_prod  linux_prod Guest OS: SUSE Linux Enterprise 11 (64-bit) Compatibility: ESXi 5.5 and later (VM version 10) VMware Tools: Not running, not installed DNS Name: IP Addresses: Host: 192.168.1.30



End of Lab Exercise 3-B



Lab Exercise 4: Monitoring and Performance Tuning


Purpose:	Perform various operations using the ScaleIO GUI and the CLI to monitor and tune a ScaleIO storage environment.
Tasks:	✓ Observing Rebalance and Rebuild using Dashboard GUI and CLI ✓ Adjusting the Rebalance and Rebuild Policy ✓ Configure Quality of Service for a ScaleIO volume ✓ Explore and reconfigure the RAM cache setting ✓ View ScaleIO reported events and ScaleIO generated log files ✓ Redirect ScaleIO event log to a centralized remote syslog server
References:	ScaleIO Lab Diagram (graphically showing relevant details for all VMs within a student pod – refer to Page 2)

Lab 4: Task 1 - Monitoring, Rebalance and Rebuild When Adding/Removing an SDS

Step	Action
	You will install and attach a new SDS to the cluster, then monitor the rebuild activity as data is redistributed to the new SDS. Then, you'll disconnect the new SDS and watch it rebuild the data from the surviving SDS nodes.
1.	On dc, close and re-open open the ScaleIO GUI, logging into the Linux ScaleIO Cluster (192.168.1.10 or 192.168.1.11). Reminder: use admin/P@ssw0rd.  Once logged in, notice that at this point we have 4 SDSs in the environment. 

Step	Action
2.	Go to the Backend view, sort by SDSs, and expand the Protection Domain.  Note that there is no Rebuild or Rebalance activity at the moment.
3.	From dc, open a Remote Desktop Session to Win-3 (192.168.1.22). Hint: Click Start and type the word “remote” in the box provided. Remote Desktop will appear among the available choices above the box. Log in as “administrator” and use the password “P@ssw0rd”.
4.	On Win-3 go to Server Manager→Storage→Disk Management, confirm the presence of Disk 2 as a 105 GB disk device. 

Step	Action
5.	On the Win-3 server, right-click Start (lower-left-hand corner). Select Open Windows Explorer to the \\dc\\share\\sw\\Windows folder, and run the sds installer  Complete the installation using default values.
6.	Back on the dc server, in the ScaleIO GUI go to the Backend view. Right-click the Domain1 domain and select Add SDS. 

Step	Action
7.	On the Add SDS to Protection Domain window, input the following: Name: SDSWin3 IP Address: 192.168.1.22 Path: F Name: Disk1  Click OK when ready.

Step

Action

8. You will see Rebalance traffic, as the Domain adjusts to the presence of the new SDS.



Item	Total Capacity	Capacity In-Use	I/O Bandwidth	IOPS	Rebuild	Rebalance
 System	 520.0 GB	76.6 GB (14.7 %)	 0.0 KB/s	0	 0.0 KB/s	 61.2 MB/s
 Domain1	 520.0 GB	76.6 GB (14.7 %)	 0.0 KB/s	0	 0.0 KB/s	 61.2 MB/s
 SDS_[192.168.1.10]	 104.0 GB	15.7 GB (15.1 %)	 0.0 KB/s	0	0.0 KB/s →  0.0 KB/s	0.0 KB/s →  18.4 MB/s
 SDS_[192.168.1.11]	 104.0 GB	15.6 GB (15.0 %)	 0.0 KB/s	0	0.0 KB/s →  0.0 KB/s	0.0 KB/s →  10.7 MB/s
 SDS_[192.168.1.12]	 104.0 GB	15.7 GB (15.1 %)	 0.0 KB/s	0	0.0 KB/s →  0.0 KB/s	0.0 KB/s →  9.3 MB/s
 SDSWin2	 104.0 GB	16.0 GB (15.4 %)	 0.0 KB/s	0	0.0 KB/s →  0.0 KB/s	0.0 KB/s →  22.8 MB/s
 SDSWin3	 104.0 GB	13.5 GB (13.0 %)	 0.0 KB/s	0	0.0 KB/s →  0.0 KB/s	60.4 MB/s →  0.0 KB/s


Rebalance


 17.0 MB/s

11.5 GB left

Step	Action
9.	Connect to Lnx-1. Run the following command: <pre>scli --query_protection_domain --protection_domain_name Domain1 grep SDS</pre> Take a moment to look over the SDS section, then run the command again, filtering output for the word “rebuild”, and then again, filtering for the word “rebalance”. <pre>scli --query_protection_domain --protection_domain_name Domain1 grep -i rebuild</pre> <pre>scli --query_protection_domain --protection_domain_name Domain1 grep -i rebalance</pre> <pre>[root@Lnx-1 ~]# scli --query_protection_domain --protection_domain_name Domain1 grep -i rebuild The number of parallel rebuild/rebalance jobs: 2 Rebuild is Enabled and using Limit-Concurrent-IO policy with the following parameters: The number of parallel rebuild/rebalance jobs: 2 Rebuild is Enabled and using Limit-Concurrent-IO policy with the following parameters: 0 Bytes active fwd-rebuild capacity 0 Bytes pending fwd-rebuild capacity 0 Bytes active bck-rebuild capacity 0 Bytes pending bck-rebuild capacity 0 Bytes fwd-rebuild capacity 0 Bytes bck-rebuild capacity Backward-rebuild-reads 0 IOPS 0 Bytes per-second Backward-rebuild-writes 0 IOPS 0 Bytes per-second Forward-rebuild-reads 0 IOPS 0 Bytes per-second Forward-rebuild-writes 0 IOPS 0 Bytes per-second [root@Lnx-1 ~]# scli --query_protection_domain --protection_domain_name Domain1 grep -i rebalance The number of parallel rebuild/rebalance jobs: 2 Rebalance is Enabled and using Favor-Application-IO policy with the following parameters: The number of parallel rebuild/rebalance jobs: 2 Rebalance is Enabled and using Favor-Application-IO policy with the following parameters: 45.2 MB (46258 KB) active rebalance capacity 1.6 GB (1608 MB) pending rebalance capacity 1.6 GB (1653 MB) rebalance capacity Rebalance-reads 30 IOPS 30.8 MB (31539 KB) per-second Rebalance-writes 28 IOPS 28.4 MB (29081 KB) per-second [root@Lnx-1 ~]#</pre> Besides the zero activity shown in the bottom lines of each command’s output, note the tuning parameters shown within the upper two lines of each output.


Step	Action
10.	Return to (or re-open) the Remote Desktop session linked to Win-3. Re-open the Server Manager, go to Configuration/Services, and find the two “emc” services used by ScaleIO. They are highlighted below: Right-click them and select Stop.  The action we just performed will cause the SDS on Win3 to go offline. Note the Alert that shows up in the SDS pane of the GUI Dashboard view.  You may also go to the GUI Alert view for more specific information. 



Step	Action																
11.	On the Dashboard view: note the Rebuild activity that is reported.  The screenshot shows the 'System Overview' dashboard with the 'Dashboard' tab selected. It displays four main sections: Capacity: A donut chart showing storage usage. The total capacity is 520.0 GB. Usage is broken down into segments: 31.2 GB, 42.6 GB, 22.6 GB, and 86.3 GB. The remaining free space is 337.3 GB. I/O Workload: Shows current I/O activity as 0.0 KB/s and 0 IOPS. A table below provides a breakdown:<table><tr><th></th><th>Bandwidth</th><th>IOPS</th><th>I/O size</th></tr><tr><td>Read</td><td>0.0 KB/s</td><td>0</td><td>0.0 KB</td></tr><tr><td>Write</td><td>0.0 KB/s</td><td>0</td><td>0.0 KB</td></tr><tr><td>Total</td><td>0.0 KB/s</td><td>0</td><td>0.0 KB</td></tr></table> Rebalance: Shows 0.0 KB/s and 0.0 KB left. Rebuild: Shows active rebuild activity at 132.2 MB/s with 11.2 GB left.		Bandwidth	IOPS	I/O size	Read	0.0 KB/s	0	0.0 KB	Write	0.0 KB/s	0	0.0 KB	Total	0.0 KB/s	0	0.0 KB
	Bandwidth	IOPS	I/O size														
Read	0.0 KB/s	0	0.0 KB														
Write	0.0 KB/s	0	0.0 KB														
Total	0.0 KB/s	0	0.0 KB														
12.	Go to the Lnx-1 Putty session and re-run the two commands showing Rebuild and Rebalance activity. What are the IOPS levels? Rebuild _____ Rebalance _____ <pre>[root@Lnx-1 ~]# sccli --query_protection_domain --protection_domain_name Domain1 grep -i rebuild The number of parallel rebuild/rebalance jobs: 2 Rebuild is Enabled and using Limit-Concurrent-IO policy with the following parameters: The number of parallel rebuild/rebalance jobs: 2 Rebuild is Enabled and using Limit-Concurrent-IO policy with the following parameters: 180.7 MB (184997 KB) active fwd-rebuild capacity 5.0 GB (5153 MB) pending fwd-rebuild capacity 0 Bytes active bck-rebuild capacity 0 Bytes pending bck-rebuild capacity 5.2 GB (5334 MB) fwd-rebuild capacity 0 Bytes bck-rebuild capacity Backward-rebuild-reads 0 IOPS 0 Bytes per-second Backward-rebuild-writes 0 IOPS 0 Bytes per-second Forward-rebuild-reads 119 IOPS 119.8 MB (122675 KB) per-second Forward-rebuild-writes 120 IOPS 120.2 MB (123084 KB) per-second [root@Lnx-1 ~]# sccli --query_protection_domain --protection_domain_name Domain1 grep -i rebalance The number of parallel rebuild/rebalance jobs: 2 Rebalance is Enabled and using Favor-Application-IO policy with the following parameters: The number of parallel rebuild/rebalance jobs: 2 Rebalance is Enabled and using Favor-Application-IO policy with the following parameters: 0 Bytes active rebalance capacity 0 Bytes pending rebalance capacity 0 Bytes rebalance capacity Rebalance-reads 0 IOPS 0 Bytes per-second Rebalance-writes 0 IOPS 0 Bytes per-second [root@Lnx-1 ~]#</pre> Note: The Backend view of the Dashboard provides more detail regarding rebuild traffic.																


Step	Action
13.	Once the rebuilds complete, return to (or re-open) the Remote Desktop session to Win-3. Re-open the Server Manager, go to Configuration/Services, and find the two “emc” services used by ScaleIO that you previously stopped. Right-click them, and select Start. Go to the dc Dashboard and note the rebuild and/or rebalance activity. 
14.	Go to the Lnx-1 Putty session and re-run the two commands showing Rebuild and Rebalance activity. What are the IOPS levels? Rebuild _____ Rebalance _____ <pre>[root@Lnx-1 ~]# scl --query_protection_domain --protection_domain_name Domain1 --show_sds 1 grep -i rebuild The number of parallel rebuild/rebalance jobs: 2 Rebuild is Enabled and using Limit-Concurrent-IO policy with the following parameters: 0 Bytes active fwd-rebuild capacity 0 Bytes pending fwd-rebuild capacity 0 Bytes active bck-rebuild capacity 0 Bytes pending bck-rebuild capacity 0 Bytes fwd-rebuild capacity 0 Bytes bck-rebuild capacity Backward-rebuild-reads 0 IOPS 0 Bytes per-second Backward-rebuild-writes 0 IOPS 0 Bytes per-second Forward-rebuild-reads 0 IOPS 0 Bytes per-second Forward-rebuild-writes 0 IOPS 0 Bytes per-second [root@Lnx-1 ~]# scl --query_protection_domain --protection_domain_name Domain1 --show_sds 1 grep -i rebalance The number of parallel rebuild/rebalance jobs: 2 Rebalance is Enabled and using Favor-Application-IO policy with the following parameters: 65.3 MB (66900 KB) active rebalance capacity 12.8 GB (13066 MB) pending rebalance capacity 12.8 GB (13131 MB) rebalance capacity Rebalance-reads 20 IOPS 20.2 MB (20684 KB) per-second Rebalance-writes 14 IOPS 14.6 MB (14950 KB) per-second</pre>
15.	When the Rebalance completes, the task is complete.

Lab 4: Task 2 - Adjusting Rebuild and Rebalance Policy

Step	Action
------	--------

Step	Action																																			
	You will use scli commands to change the rebuild and rebalance policies, then monitor the effects.																																			
1.	Once rebalance completes, adjust the rebuild policy to no_limits, and re-check the tuning parameters. <pre>scli --set_rebuild_policy --protection_domain_name Domain1 --storage_pool_name Cap_Pool --policy no_limit</pre> <pre>scli --query_protection_domain --protection_domain_name Domain1</pre> <pre>[root@LnX-1 ~]# scli --set_rebuild_policy --protection_domain_name Domain1 --storage_pool_name Cap_Pool --policy no_limit This setting might effect the speed of rebuild/rebalance, or degrade the performance of application IOs. Press 'y' to confirm that you want to proceed ? Rebuild policy on Storage Pool Cap_Pool in Protection Domain Domain1 modified successfully [root@LnX-1 ~]# scli --query_protection_domain --protection_domain_name Domain1 Protection Domain Domain1 (Id: 3b45ef3100000000) has 1 storage pools, 1 Fault Sets, 5 SDS nodes, 4 volumes and 144 .0 GB (147456 MB) available for volume allocation Operational state is Active Storage Pool Cap_Pool (Id: 1c09c63700000000) has 4 volumes and 144.0 GB (147456 MB) available for volume allocatio n The number of parallel rebuild/rebalance jobs: 2 Rebuild is Enabled and using No-Limit policy Rebalance is Enabled and using Favor-Application-IO policy with the following parameters: Number of concurrent IOs per device: 1, Bandwidth limit per device: 10240 KB per second Zero padding is disabled Spare policy: 26% out of total RAM cache is used RAM cache write handling mode is 'passthrough'</pre>																																			
2.	Return to (or re-open) the Remote Desktop session linked to Win-3. Re-open the Server Manager, go to Configuration/Services, and find the two “emc” services used by ScaleIO. They are highlighted below: Right-click them and select Stop. <table><tr><td>Distributed Link Tracking Client</td><td>Maintains links between...</td><td>Started</td><td>Automatic</td><td>Loc</td></tr><tr><td>Distributed Transaction Coord...</td><td>Coordinates transactio...</td><td>Started</td><td>Automatic (D...</td><td>Net</td></tr><tr><td>DNS Client</td><td>The DNS Client service ...</td><td>Started</td><td>Automatic</td><td>Net</td></tr><tr><td>emc data server</td><td>scaleio Data Server – E...</td><td>Started</td><td>Automatic</td><td>Loc</td></tr><tr><td>emc shared memory server</td><td>Provides shared memor...</td><td>Started</td><td>Automatic</td><td>Loc</td></tr><tr><td>Encrypting File System (EFS)</td><td>Provides the core file e...</td><td></td><td>Manual</td><td>Loc</td></tr><tr><td>Extensible Authentication Pr...</td><td>The Extensible Authent...</td><td></td><td>Manual</td><td>Loc</td></tr></table>	Distributed Link Tracking Client	Maintains links between...	Started	Automatic	Loc	Distributed Transaction Coord...	Coordinates transactio...	Started	Automatic (D...	Net	DNS Client	The DNS Client service ...	Started	Automatic	Net	emc data server	scaleio Data Server – E...	Started	Automatic	Loc	emc shared memory server	Provides shared memor...	Started	Automatic	Loc	Encrypting File System (EFS)	Provides the core file e...		Manual	Loc	Extensible Authentication Pr...	The Extensible Authent...		Manual	Loc
Distributed Link Tracking Client	Maintains links between...	Started	Automatic	Loc																																
Distributed Transaction Coord...	Coordinates transactio...	Started	Automatic (D...	Net																																
DNS Client	The DNS Client service ...	Started	Automatic	Net																																
emc data server	scaleio Data Server – E...	Started	Automatic	Loc																																
emc shared memory server	Provides shared memor...	Started	Automatic	Loc																																
Encrypting File System (EFS)	Provides the core file e...		Manual	Loc																																
Extensible Authentication Pr...	The Extensible Authent...		Manual	Loc																																







Step	Action
3.	Go to the dc Dashboard and note the rebuild and rebalance activity.  The screenshot shows the dc Dashboard with four main sections: Capacity: A donut chart showing storage usage. Total capacity is 395.0 GB. Used capacity is 242.1 GB. Free capacity is 152.9 GB. The chart is divided into segments: 23.7 GB (blue), 46.5 GB (green), 19.0 GB (orange), and 63.7 GB (red). I/O Workload: Shows 0.0 KB/s bandwidth and 0 IOPS. A table below shows Read, Write, and Total IOPS and bandwidth are all 0.0 KB/s. Rebalance: Shows 0.0 KB/s bandwidth and 0.0 KB left. Rebuild: Shows 163.4 MB/s bandwidth and 9.5 GB left. What are the IOPS? Rebuild _____ Rebalance _____ Do you observe a change in IOPS relative to the constrained case in Task 1? _____
4.	Have a look at the dc GUI Backend view and observe the trend in the Capacity In Use column entry for each SDS server. Are these trends what you would expect? _____
5.	Now, adjust the <u>rebalance</u> policy to no_limits, and re-check the tuning parameters. <pre>scli --set_rebalance_policy --protection_domain_name Domain1 --storage_pool_name Cap_Pool --policy no_limit</pre> <pre>scli --query_protection_domain --protection_domain_name Domain1 grep -i rebalance</pre>  The terminal output shows the following: - Command: <code>scli --set_rebalance_policy --protection_domain_name Domain1 --storage_pool_name Cap_Pool --policy no_limit</code> - Message: "This setting might effect the speed of rebuild/rebalance, or degrade the performance of application IOs. Press 'y' to confirm proceed ?" - Response: 'y' - Message: "Rebalance policy on Storage Pool Cap_Pool in Protection Domain Domain1 modified successfully" - Command: <code>scli --query_protection_domain --protection_domain_name Domain1 grep -i rebalance</code> - Output: <pre> The number of parallel rebuild/rebalance jobs: 2 Rebalance is Enabled and using No-Limit policy The number of parallel rebuild/rebalance jobs: 2 Rebalance is Enabled and using Favor-Application-IO policy with the following parameters: 0 Bytes active rebalance capacity 0 Bytes pending rebalance capacity 0 Bytes rebalance capacity Rebalance-reads 0 IOPS 0 Bytes per-second Rebalance-writes 0 IOPS 0 Bytes per-second </pre>
6.	Return to (or re-open) the Remote Desktop session linked to Win-3. Re-open the Server Manager, go to Configuration/Services, and find the two “emc” services used by ScaleIO that you previously stopped. Right-click them and select Start.

Step	Action
7.	Go back to dc, open the ScaleIO GUI and note the rebuild and/or rebalance activity. What are the IOPS? Rebuild _____ Rebalance _____ Did you get a greater IOPS rate for the Rebuild or the Rebalance? _____ Can you provide one possible reason for this? _____ (Hint: Make a list of the server-pairs involved during chunk copies in your case – first during the Rebuild, then during the Rebalance).
8.	Choose the Backend view, by Storage Pool. Right-click on the Cap_Pool Storage Pool and select Set I/O Priority. Note that from this screen, you have additional tuning options for ScaleIO throttling. 

Lab 4: Task 3 - Configuring QoS for a Volume

Step	Action
	Using scli, experiment with different volume limits.


Step	Action
1.	From within a Putty session to the MDM Primary (should be Lnx-1), log into the MDM cluster as admin, if you are not admin already. Run the following command: <pre>scli --query_sdc_volume_limits --volume_name vol2 --sdc_ip 192.168.1.11</pre> <pre>[root@lnx-1 ~]# scli --query_sdc_volume_limits --volume_name vol2 --sdc_ip 192.168.1.11 sdc volume limits will be changed. Press 'y' to confirm that you want to proceed ? Successfully queried limits from SDC 192.168.1.11 to volume vol2:IOPS limit is unlimited.Bandwidth limit is unlimited.</pre> Note: The IP address 192.168.1.11 is Lnx-2, the server to which vol2 is currently mapped.
2.	Return to (or re-open) a Putty session to <u>Lnx-2</u>. On Lnx-2, generate some I/O activity to the ScaleIO volume. In your home directory /root, we have provided a script writefile.bash that will work fine for this purpose: it performs small-block sequential writes to a file called largefile in the filesystem layered on the ScaleIO device. When largefile reaches a filesize of ~4 GB, the script exits. Examine, and then run, the script writefile.bash on Lnx-2: <pre>cd /root ls -l writefile.bash cat writefile.bash ./writefile.bash</pre>


Step	Action
3.	Look at the MB/sec or IOPS load shown on the Dashboard. <i>Remember that it's a running average, so allow the figures displayed to refresh two or three times for an accurate count.</i>  NOTE: The writefile.bash script is designed to run only for a short period (minutes or less, depending on prevailing system load). If you notice the GUI is reporting 0 IOPs, that probably means the script has completed execution. As and when you need load on the ScaleIO volume vol2, rerun the ./writefile.bash command.
4.	Now, restrict the IOPS for the volume. Run this command on the Primary MDM: <pre>scli --set_sdc_volume_limits --volume_name vol2 --sdc_ip 192.168.1.11 --limit_iops 10</pre>  Note: An IOPS limit of 10 is the lowest possible setting.
5.	Look at the IOPS load shown on the Dashboard view. What is it now? _____ Experiment with higher IOPs settings – try 20 and 30, for example. Observe the changes.    



Step	Action
6.	On Lnx-1: restore the volume configuration to the original state, before proceeding to the next task. Return the IOPS limit to zero, which is unlimited. <pre>[root@Lnx-1 1]# scli --set_sdc_volume_limits --volume_name vol2 --sdsc_ip 192.168.1.11 --limit_iops 0 Successfully modified limits from SDC 192.168.1.11 to volume vol2:IOPS limit set to unlimited.</pre>
7.	On Lnx-2: make sure to terminate your “writefile.bash” workload. This will help eliminate unnecessary load on the lab equipment. On your PuTTY session to Lnx-2, repeatedly issue <Ctrl>-C until you get your root@Lnx-2 shell prompt again.

Lab 4: Task 4 - RAM Cache Determination and Implementation

Step	Action
	You will create a new storage pool, which will utilize RAM cache.
1.	From within a Putty session to the MDM Primary (should be Lnx-1), log into the MDM cluster as admin, if you are not admin already. Run the following command: <pre>scli --query_protection_domain --protection_domain_name Domain1 less</pre>
2.	Look at the information for the Storage Pool named Cap_Pool. Is RAM cache being used for the Pool? Yes / No If so, what mode? _____ Look at the information for the SDS's. Is the SDS RAM cache information listed? Yes / No

Step	Action
3.	On the MDM, run the following command to look more closely at SDSWin2: <pre>scli --query_sds --sds_name SDSWin2</pre> Is the SDS RAM cache information listed? Yes / No If so, 1) What is its size in KB? _____ 2) Is it enabled? Yes / No
4.	Back on the dc server, in the Dashboard go to the Backend view. Right-click on the Domain1 and select Add Storage Pool. The name of the new Storage Pool is Perf_Pool. Select Use RAM Cache.  When finished, click OK. Click Close when complete.

Step	Action
5.	Back on the dc server, go to the ScaleIO GUI → Backend view. Sort by SDSs. Right-click on the SDSLn timer 1 SDS and select Add Device. The Device Path and Name is /dev/sdc and the Storage Pool is Perf_Pool.  When finished, click OK. Click Close when complete. Repeat these steps to add the /dev/sdc of SDSLn timer 2 and SDSLn timer 3 to Perf_Pool.

Step	Action
6.	Check if any of your newly added devices has a yellow background (as below). If it does, it means that the device is not active, and should be activated (next step).  If you don't see the yellow background, the devices are already active and ready for ScaleIO to use. Skip the next step and proceed directly to Step 7.
7.	Activate all of the inactive devices - right-click on the device, and select Activate Device: 

Step	Action
8.	Back on the Primary MDM, run the following command: <pre>scli --query_protection_domain --protection_domain_name Domain1 less</pre> Look at the information for the Storage Pool named Perf_Pool. Is RAM Cache being used for the Pool? Yes / No _____

Lab 4: Task 5 - Monitoring ScaleIO-reported Events

Step	Action
1.	From within a Putty session to the MDM Primary (should be Lnx-1), log into the MDM cluster as admin, if you are not admin already. Note: For a quick refresher on how to do this, refer to Lab3, Tasks 2 and 3. Run the following command: <pre>cd /opt/emc/scaleio/mdm/logs</pre> <pre>ls -al</pre> <pre>[root@Lnx-1 logs]# cd /opt/emc/scaleio/mdm/logs [root@Lnx-1 logs]# ls -al total 105656 drwx-----. 2 root root 4096 Jun 24 14:20 . drwxr-xr-x. 7 root root 4096 Jun 19 11:35 .. -rw-r--r--. 1 root root 199 Jun 19 11:35 emc-scaleio-mdm-install.log -rw-r--r--. 1 root root 25600 Jun 24 14:20 eventlog.db -rw-r--r--. 1 root root 289646 Jun 24 14:23 exp.0 -rw-r--r--. 1 root root 1200070 Jul 1 08:53 trc.0 -rw-r--r--. 1 root root 26217908 Jun 24 13:25 trc.1 -rw-r--r--. 1 root root 27548551 Jun 24 13:13 trc.2 -rw-r--r--. 1 root root 26292469 Jun 24 13:11 trc.3 -rw-r--r--. 1 root root 26583384 Jun 24 13:09 trc.4</pre>

Step	Action
2.	This is where ScaleIO keeps its logs. ScaleIO sees certain activities (events) as worthy of note, and notes them within eventlog.db. Still in the same directory, run the following command: <pre>file eventlog.db</pre> What type of file is eventlog.db? _____
3.	Still in the same directory, run the following command: <pre>more eventlog.db</pre> While you can read some of this, it is not in a helpful format. Fortunately, ScaleIO has a tool to assist with this. Now, switch directories and run: <pre>cd /opt/emc/scaleio/mdm/bin</pre> <pre>./showevents.py</pre> Some of the events displayed should look familiar.

Step	Action																																				
4.	Now run the same command with <code>--help</code>: <pre>./showevents.py --help</pre> <pre>[root@Lnx-1 bin]# ./showevents.py --help Usage: showevents.py [options] Options: -h, --help show this help message and exit --min_severity=MIN_SEVERITY Specify minimal severity --severity=SEVERITY Specify severity --from_id=ID_FROM Limit by ID --to_id=ID_TO Limit by ID --from_date=DATE_FROM Limit by from Date. Date format is same as it shown in event log (YYYY-MM-DD HH:MM:SS) For example January 1st 2013 09:00PM is 2013-01-01 09:00:00 --to_date=DATE_TO Limit by to Date. Date format is same as it shown in event log (YYYY-MM-DD HH:MM:SS) For example January 1st 2013 09:00PM is 2013-01-01 09:00:00 -g GREP, --grep=GREP Search specific word --full Show full event</pre> As you can see, you can filter events by date range, by severity, and even search (grep) for key words.																																				
5.	Return to (or re-open) the Remote Desktop session linked to Win-3. Re-open the Server Manager, go to Configuration/Services, and find the two “emc” services used by ScaleIO. They are highlighted below: Right-click them and select “Stop”. <table><tr><td></td><td>Distributed Transaction Coord...</td><td>Coordinates transactio...</td><td>Started</td><td>Automatic (D...</td><td>Net</td></tr><tr><td></td><td>DNS Client</td><td>The DNS Client service ...</td><td>Started</td><td>Automatic</td><td>Net</td></tr><tr><td></td><td>emc data server</td><td>scaleio Data Server – E...</td><td>Started</td><td>Automatic</td><td>Loc</td></tr><tr><td></td><td>emc shared memory server</td><td>Provides shared memor...</td><td>Started</td><td>Automatic</td><td>Loc</td></tr><tr><td></td><td>Encrypting File System (EFS)</td><td>Provides the core file e...</td><td></td><td>Manual</td><td>Loc</td></tr><tr><td></td><td>Extensible Authentication Pr...</td><td>The Extensible Authent...</td><td></td><td>Manual</td><td>Loc</td></tr></table>		Distributed Transaction Coord...	Coordinates transactio...	Started	Automatic (D...	Net		DNS Client	The DNS Client service ...	Started	Automatic	Net		emc data server	scaleio Data Server – E...	Started	Automatic	Loc		emc shared memory server	Provides shared memor...	Started	Automatic	Loc		Encrypting File System (EFS)	Provides the core file e...		Manual	Loc		Extensible Authentication Pr...	The Extensible Authent...		Manual	Loc
	Distributed Transaction Coord...	Coordinates transactio...	Started	Automatic (D...	Net																																
	DNS Client	The DNS Client service ...	Started	Automatic	Net																																
	emc data server	scaleio Data Server – E...	Started	Automatic	Loc																																
	emc shared memory server	Provides shared memor...	Started	Automatic	Loc																																
	Encrypting File System (EFS)	Provides the core file e...		Manual	Loc																																
	Extensible Authentication Pr...	The Extensible Authent...		Manual	Loc																																
6.	Go to the Lnx-1 Putty session and run the command to view the log: <pre>./showevents.py</pre> <pre>173 2014-07-02 11:16:51.349 CLI_COMMAND_SUCCEEDED INFO Command modify_sdc_volume_limit succeeded. 174 2014-07-02 11:17:05.300 MDM_CLI_COMMAND_RECEIVED INFO Command modify_sdc_volume_limit received, User: 'admin'. 175 2014-07-02 11:17:05.386 CLI_COMMAND_SUCCEEDED INFO Command modify_sdc_volume_limit succeeded. 176 2014-07-02 11:30:48.147 SDS_DISCONNECTED ERROR SDS: SDSWin3 IP: 192.168.1.22 (id: 8c79d30600000005) disconnected. 177 2014-07-02 11:30:48.998 MDM_DATA_DEGRADED ERROR The system is now in DEGRADED state.</pre>																																				

Step	Action
7.	Return to the Win-3 Remote Desktop session and start the emc services. Go to the Lnx-1 Putty session and run the command to view the log: ./showevents.py <pre> 176 2014-07-02 11:30:48.147 SDS_DISCONNECTED ERROR SDS: SDSWin3 IP: 192.168.1.22 (id: 8c79d30600000005) disconnected. 177 2014-07-02 11:30:48.998 MDH_DATA_DEGRADED ERROR The system is now in DEGRADED state. 178 2014-07-02 11:33:29.723 MDH_DATA_NORMAL INFO The system is now in NORMAL state. 179 2014-07-02 11:34:21.909 SDS_RECONNECTED INFO SDS: SDSWin3 (ID 8c79d30600000005) reconnected </pre>

Lab 4: Task 6 - Set Up Centralized RSyslog Server for ScaleIO Event Logging

Step	Action
1.	Our first step is to identify the host that we will configure as our centralized RSYSLOG server. This is the target syslog server to which ScaleIO events will be redirected. For this lab we will use the ScaleIO TB server (Lnx-3, 192.168.1.12) as our target server. Using PuTTY, login to the Lnx-3 server with the credentials root/P@ssw0rd.
2.	On Lnx-3, check the status of the Linux firewall – the status right now, and the expected status after a reboot: service iptables status Observe that the firewall is currently not running. chkconfig --list iptables The output of chkconfig (“off” for all runlevels 0 through 6) tells us that the firewall service will never automatically start on this host, whenever it starts up. This means that Lnx-3 has unrestricted access on both incoming and outgoing TCP traffic. <u>You can proceed to Step 3 right now.</u>
3.	On Lnx-3, examine the /etc/rsyslog.conf file, and make suitable changes to it, following the instructions provided below. Take a look at the default configuration file /etc/rsyslog.conf : more /etc/rsyslog.conf and page through to the end of the file, using the <Space> bar.

Step	Action
4.	For your convenience, we have provided you “before” and “after” versions of the rsyslog.conf file to enable centralized logging for ScaleIO. These versions are in the /root home directory for your reference: <pre>ls -l /root/rsyslog*</pre> You should see two rsyslog-related files listed in root’s home directory - rsyslog.conf.orig and rsyslog.conf.new, as shown below: <pre>[root@LnX-3 etc]# ls -l /root/rsyslog* -rw-r--r--. 1 root root 2826 Aug 18 16:05 /root/rsyslog.conf.new -rw-r--r--. 1 root root 2741 May 20 2009 /root/rsyslog.conf.orig [root@LnX-3 etc]#</pre>
5.	Ensure that the file /root/rsyslog.conf.orig is exactly the same as your current /etc/rsyslog.conf: <pre>diff /etc/rsyslog.conf /root/rsyslog.conf.orig</pre> No differences should be reported.
6.	On LnX-3, examine the needed changes in the rsyslog.conf file: <pre>diff /root/rsyslog.conf.orig /root/rsyslog.conf.new</pre> <pre>[root@LnX-3 ~]# diff /root/rsyslog.conf.orig /root/rsyslog.conf.new 13,14c13,14 < #ModLoad imudp.so < #UDPServerRun 514 --- > \$ModLoad imudp.so > \$UDPServerRun 514 17,18c17,18 < #ModLoad imtcp.so < #InputTCPServerRun 514 --- > \$ModLoad imtcp.so > \$InputTCPServerRun 514 39c39 < *.info;mail.none;authpriv.none;cron.none /var/log/messages --- > *.info;mail.none;authpriv.none;cron.none local0.none /var/log/ messages 60c60,61 < --- > \$template ScaleIOmsg, "/var/log/%PROGRAMNAME%.log" > local0.* ?ScaleIOmsg</pre>

Step	Action
7.	Observe the following differences. The first four modified lines (beginning with \$ModLoad or \$Input) are just uncommented lines, i.e., the preceding # has been removed. The redirection to the /var/log/messages file has been enhanced to include the local0 facility – this is the rsyslog facility we will use for ScaleIO event logging. The last two lines for the ScaleIO rsyslog template are new. They indicate that facility local0 should be used for ScaleIO logging, and specify that the logging should be directed to a file in the /var/log directory with the file name as provided.
8.	On Lnx-3, now that we understand the needed changes, let's actually make them and activate them. First, replace the /etc/rsyslog.conf file with the modified version: <pre>cp /root/rsyslog.conf.new /etc/rsyslog.conf</pre> Next, restart the RSYSLOG service for the configuration changes to take effect: <pre>service rsyslog restart</pre>
9.	On the target RSYSLOG server Lnx-3, check if the server is listening on port 514: <pre>netstat -uanp grep rsyslog</pre> You should see results as below: <pre>udp 0 0 0.0.0.0:514 0.0.0.0:* 3589/rsyslogd udp 0 0 :::514 :::* 3589/rsyslogd</pre> This completes the configuration for the centralized target logging server. Next, let's configure the ScaleIO cluster to direct event logging traffic to the target server.
10.	On the Primary MDM server Lnx-1, run the following scli commands, to perform the desired redirection for rsyslog (making sure to first login as admin/P@ssw0rd to ScaleIO): <pre>scli --login --username admin --password P@ssw0rd</pre> <pre>scli --stop_remote_syslog</pre> <pre>scli --start_remote_syslog --remote_syslog_server_ip 192.168.1.12 --remote_syslog_server_port 514</pre>

Step	Action
11.	On primary MDM server Lnx-1: perform similar steps as we did previously for the target host Lnx-3 (steps 2 through 5, listed below for your convenience): <pre>service iptables status</pre> <pre>chkconfig --list iptables</pre> The above commands confirm that the firewall will not block any outgoing traffic from Lnx-1. <pre>diff /etc/rsyslog.conf /root/rsyslog.conf.orig</pre> This shows the rsyslog.conf.orig file is the same as the currently active configuration file. <pre>diff /root/rsyslog.conf.orig /root/rsyslog.conf.new</pre> This will show only the following change, which clearly suggests that all syslog traffic from this host, Lnx-1, is to be redirected to the Lnx-3 host on TCP port 514 (which is the port it is listening on): <pre>< *.* @@remote-host:514</pre> <pre>> *.* @@192.168.1.12:514</pre> <pre>cp /root/rsyslog.conf.new /etc/rsyslog.conf</pre> <pre>service rsyslog restart</pre> The two commands above will cause, and activate, the needed change to rsyslog.conf on the Lnx-1 host.
12.	Repeat all commands within Step 8 on the secondary MDM server Lnx-2. What is the purpose of doing this? Wouldn't the primary server Lnx-1 generate all the events to be logged? _____





Step	Action
13.	Now, let's validate that the centralized rsyslog server Lnx-3 is receiving logs from the clients. First, confirm that Lnx-1 is the primary MDM, and Lnx-2 is the secondary MDM. You can do this with the scli --query_cluster command. The Primary MDM will result in output similar to this: <pre data-bbox="219 409 1075 613">[root@Lnx-1 ~]# scli --query_cluster Mode: Cluster, Cluster State: Normal, Tie-Breaker State: Connected Primary IP: 192.168.1.10 Secondary IP: 192.168.1.11 Tie-Breaker IP: 192.168.1.12 Management IP: 192.168.1.10, 192.168.1.11 Name: N/A [root@Lnx-1 ~]#</pre> If you run the same scli --query_cluster command on the Secondary MDM, you will see output similar to this: <pre data-bbox="219 772 1263 861">[root@Lnx-2 ~]# scli --query_cluster Error: MDM failed command. Status: Use the cluster virtual IP or the primary MDM physical IP to access the cluster [root@Lnx-2 ~]#</pre>
14.	On the Primary MDM (Lnx-1, 192.168.1.10), run the command: scli --switch_mdm_ownership
15.	Wait about 15 seconds and check the /var/log folder on the central rsyslog server (Lnx-3 in this exercise). You should see a file named EMC-ScaleIO.log.
16.	On Lnx-3, check the contents of this log file. You should see entries representing the MDM switch ownership commands just run. In the example below, Lnx-2 (192.168.1.11) is now the Primary MDM. <pre data-bbox="219 1302 1304 1535">Aug 5 04:20:23 Lnx-2 EMC-ScaleIO -[Initialized the remote syslog module] Aug 5 12:14:28 Lnx-2 EMC-ScaleIO -[This MDM is switching to Master mode. MDM will start running.] Aug 5 12:14:33 Lnx-2 EMC-ScaleIO -[SDS: SDS_Lnx2 (ID 95c0773b00000000) reconnected] Aug 5 12:14:33 Lnx-2 EMC-ScaleIO -[SDS: SDS_Lnx1 (ID 95c0773c00000002) reconnected] Aug 5 12:14:33 Lnx-2 EMC-ScaleIO -[SDS: SDS_Lnx3 (ID 95c0773c00000001) reconnected] Aug 5 12:14:33 Lnx-2 EMC-ScaleIO -[SDS: SDS_Win2 (ID 95c09e4b00000004) reconnected] Aug 5 12:14:33 Lnx-2 EMC-ScaleIO -[SDC connected. ID: 64022b1a00000001; IP: 192.168.1.11; GUID: 1DDB2C2E-2D02-41AE-BB28-10EEF0537A0C] Aug 5 12:14:33 Lnx-2 EMC-ScaleIO -[SDC connected. ID: 64022b1b00000002; IP: 192.168.1.12; GUID: BD9DAA80-16C3-4043-AB11-380F083A22DE] Aug 5 12:14:33 Lnx-2 EMC-ScaleIO -[SDC connected. ID: 64022b1900000000; IP: 192.168.1.10; GUID: FE5CA99B-4D67-46D4-A09C-A8C6C36AADF8]</pre>

Step	Action
17.	On the new primary MDM Lnx-2: run the command <pre>scli --switch_mdm_ownership</pre> Note that the centralized log file /var/log/EMC-ScaleIO.log shows that the Primary MDM is now back to Lnx-1 (192.168.1.10): <pre>Aug 5 12:14:28 Lnx-1 EMC-ScaleIO -[Initialized the remote syslog module] Aug 5 12:19:09 Lnx-1 EMC-ScaleIO -[This MDM is switching to Master mode. MDM will start running.] Aug 5 12:19:12 Lnx-1 EMC-ScaleIO -[SDS: SDS_Lnx2 (ID 95c0773b00000000) reconnected] Aug 5 12:19:12 Lnx-1 EMC-ScaleIO -[SDS: SDS_Lnx3 (ID 95c0773c00000001) reconnected] Aug 5 12:19:12 Lnx-1 EMC-ScaleIO -[SDS: SDS_Lnx1 (ID 95c0773d00000002) reconnected] Aug 5 12:19:12 Lnx-1 EMC-ScaleIO -[SDS: SDS_Win2 (ID 95c09e4b00000004) reconnected] Aug 5 12:19:12 Lnx-1 EMC-ScaleIO -[SDC connected. ID: 64022b1900000000; IP: 192.168.1.10; GUID: FE5CA99B-4D67-46 -A09C-A8C6C36AADF8] Aug 5 12:19:12 Lnx-1 EMC-ScaleIO -[SDC connected. ID: 64022b1b00000002; IP: 192.168.1.12; GUID: BD9DAA80-16C3-40 -AB11-380F083A22DE] Aug 5 12:19:12 Lnx-1 EMC-ScaleIO -[SDC connected. ID: 64022b1a00000001; IP: 192.168.1.11; GUID: 1DDB2C2E-2D02-41 -BB28-10EEF0537A0C] Aug 5 12:19:13 Lnx-1 EMC-ScaleIO -[SDC connected. ID: 6402522900000003; IP: 192.168.1.21; GUID: 62F30EE7-E8B3-C7 -B1A0-1FC716FF8EF3]</pre> This confirms that both Lnx-1 and Lnx-2 are successfully performing redirection of ScaleIO events whenever either one becomes the primary.

Lab Exercise 5-A: Exercising the ScaleIO REST API


Purpose:	Use a graphical browser-based REST client to issue standard REST calls to a ScaleIO cluster and verify the results.
Tasks:	✓ Validate that the REST gateway has a functional connection to the ScaleIO MDM ✓ Install and prepare a Firefox browser-based REST client ✓ Issue “GET” and “POST” calls to a ScaleIO instance using the REST client
Reference:	ScaleIO Lab Diagram (graphically showing relevant details for all VMs within a student pod – refer to Page 2)




Lab 5-A: Task 1 - Verify REST Gateway Connection to the ScaleIO Instance

Step	Action
1.	Open a Browser on the DC. Connect to https://dc.emc.edu/rest.jsp 
2.	It will prompt you to login to the Installer: use U: admin P: P@ssw0rd 
3.	It will prompt you to connect to the REST Gateway. Click the link 
4.	Enter admin P@ssw0rd as the credentials (these are the MDM credentials) 


Step	Action										
5.	It will automatically run some basic queries, and validate the REST configuration Obtained login token for the MDM. Successfully retrieved system information from the MDM. This page connects to the REST Gateway's configured MDM to perform few basic queries in order to validate its con MDM Cluster System Information <table> <thead> <tr> <th>Property</th><th>Value</th></tr> </thead> <tbody> <tr> <td>Name</td><td></td></tr> <tr> <td>Secondary mdm actor port</td><td>9011</td></tr> <tr> <td>System version name</td><td>EMC ScaleIO Version: R1_32.403.2</td></tr> <tr> <td>Tiebreaker mdm actor port</td><td>9011</td></tr> </tbody> </table>	Property	Value	Name		Secondary mdm actor port	9011	System version name	EMC ScaleIO Version: R1_32.403.2	Tiebreaker mdm actor port	9011
Property	Value										
Name											
Secondary mdm actor port	9011										
System version name	EMC ScaleIO Version: R1_32.403.2										
Tiebreaker mdm actor port	9011										


Lab 5-A: Task 2 - Prepare the Firefox REST Client



Step	Action
1.	In the Firefox browser, click on the red RESTClient link, in the upper-right corner 
2.	It will launch the client 

Step	Action
3.	We've prepared some requests in advance, click Favorite Requests → Import Favorite Requests 
4.	Browse to c:\share\misc, select "Validated...json" and click Open 
5.	They will not appear (minor bug in client). <u>Repeat step 4</u>, and they will appear 

Lab 5-A: Task 3 - Issue “GET” and “POST” Requests to ScaleIO



Step	Action
1.	Load our first practice REST call, get_gateway_configuration. From Favorite Requests, select the preloaded request get_gateway_configuration. Observe the three items:  Note that the REST Method is automatically selected as GET for this saved call. Note the syntax of the URL to get the REST gateway’s configuration. Also, note that the Content-Type shows the value application-json. If you ever need to change to another type, you can use the Headers drop-down for doing this.
2.	Specify the credentials for your REST gateway. The saved query that we just imported contains gateway credentials from another installation. Since we need to authenticate to our specific REST gateway, we need to change to our gateway’s credentials. Do this as follows: First, use the X button shown, to clear out the existing credentials: 

Step	Action
3.	Next, click on Authentication (on the Menu bar above) and select Basic Authentication. In the next screen offered, specify the REST gateway username admin and the password P@ssw0rd. Check the Remember Me box and click OK.  The screenshot shows two parts of the REST client interface. On the left, a menu bar with 'File', 'Authentication', and 'Headers' is visible. The 'Authentication' dropdown menu is open, showing 'HTTP authentication' and 'Basic Authentication', with a mouse cursor pointing at 'Basic Authentication'. On the right, the 'Basic Authorization' dialog box is displayed. It has fields for 'Username' (containing 'admin') and 'Password' (containing masked characters '*****'). There is a checkbox for 'Remember me' which is currently unchecked. At the bottom right of the dialog are 'Okay' and 'Cancel' buttons, with a mouse cursor pointing at the 'Okay' button. Note: You may need to correct the credentials in this manner, before running <i>every</i> other imported query in your Favorite Requests, as you proceed through this lab exercise.
4.	Run the get_gateway_configuration query. Make sure the BODY section is left blank. This is true for all GET requests. Now that the query is filled out, click SEND, to the right of the URL.

Step	Action
5.	Examine the response: check that the REST gateway is configured with the correct IP addresses for the MDM. Look at the Response section of the REST client, below Body. Select the Response Body (Highlight) section, as shown here:  <pre> 1. { 2. "snmpResendFrequency": "0", 3. "systemId": "4b36f8677d4ecb5d", 4. "snmpSamplingFrequency": "30", 5. "mdmPort": "6611", 6. "featuresEnableSnmp": "false", 7. "featuresEnableIM": "true", 8. "snmpPort": "162", 9. "mdmUsername": "", 10. "mdmAddresses": 11. [12. "192.168.1.10", 13. "192.168.1.11" 14.], 15. "snmpTrapsReceiverIps": null </pre> In the response, ensure that your REST gateway correctly reports the primary and secondary MDM addresses as shown. This confirms that the gateway is properly configured for our specific MDM instance.
6.	Select get_all_instances from Favorite Requests, and run this new request. 


Step	Action
7.	Examine the information reported in the Response Body (Highlight) section to answer these questions: What is the installation ID of the reported instance? _____ Which is the version number of this instance? _____ What are the IP addresses of the three MDM cluster nodes? _____ _____
8.	Note: Make sure to record the id from the output as indicated here. Also, highlight it and copy/paste to a Notepad window, as it will be needed later (in a POST request): <pre data-bbox="219 724 1105 1003"> "qosTimeLeftInDays": "5", "replicationTimeLeftInDays": "5", "isInitialLicense": true, "id": "7843f2302198b8b8", "links": [{ "rel": "self", "href": "/api/instances/System:7843f2302198b8b8" }] </pre> What is the id of your ScaleIO instance? _____
9.	Get the Protection Domains configured for this instance. Load the get_protdoms_this_instance command from Favorite Requests. Examine the URL and then run it by clicking SEND. URL https://dc.emc.edu:443/api/types/ProtectionDomain/instances
10.	Review the results reported for the Protection Domain(s) in the Response Body (Highlight) pane. How many Protection Domains are reported? _____ Are the name(s) of the Protection Domain(s) reported? _____ Are you sure that the Protection Domain corresponds to your particular ScaleIO installation, and not someone else's? Why? _____



Step	Action
11.	Get the volumes that have been created in this instance. Next, load and run the get_volumes_this_instance query from Favorite Requests. URL <code>https://dc.emc.edu:443/api/types/Volume/instances</code>
12.	In the Response Body (Highlight) pane, locate an easily identifiable volume with a name that you assigned and you can recognize (for example, vol4 below): <pre>{ "name": "vol4", "creationTime": 1409256020, "mappingToAllSdcsEnabled": false, "consistencyGroupId": "0000000000000000", "ancestorVolumeId": "0000000000000000", "mappedScsiInitiatorInfo": null, "storagePoolId": "ce32103700000000", "isObfuscated": false, "volumeType": "ThickProvisioned", "vtreeId": "3e4e4d0400000003", "sizeInKb": 16777216, "mappedSdcInfo": null, "id": "f663ed5600000003", "links":</pre> Using the mouse, highlight the id reported for this volume (hex string within the quotation marks). Right-click and select Copy, then Paste to the Notepad buffer where the instance ID was saved. The Volume ID will also be needed in our POST request. We have exercised a few basic GET calls to the instance. Let's try our POST call next.

Step	Action
13.	In the Firefox REST Client, load create_snapshot from Favorite Requests. Check first that the command type has now changed to POST (it is not a GET). Using the saved results (in Notepad window), make the needed edits in the URL and in the BODY section of the POST request. In the screen shown next, there are three items you will need to change: the instance ID in the URL; volume ID, and a name you assign for the new snapshot:  Click SEND to run the REST command.
14.	Check that no errors are reported. Correct the query and rerun, if needed. Examine the contents of the Response Body (Highlight) pane. You should not see any errors being reported. If the command ran successfully, this is what the results will look like: 

Step	Action
15.	Using an SCLI command, verify that the REST POST request has run successfully. On an ssh session, as root to your Primary MDM (either 192.168.1.10 or 192.168.1.11), first authenticate as user admin; then run the command: <pre>scli --query_all_volumes</pre> Can you identify the new snapshot within the list of volumes that are reported?

Lab X: End of lab

Step	Action
	If there is spare time, you are welcome to re-do any of these exercises, or attempt to come up with your own activities in the environment. This is entirely up to you. Before you leave, please clean up the lab environment for the next student assigned your account.
1.	In From the main vCloud Director screen → Home page, click on the stop button on your vApp 

Step	Action
2.	Wait for it to go from stopping to stopped, then right-click the vApp and click Delete  The screenshot shows the vApp etech1-01_1 interface. On the left, a card displays 'vApp etech1-01_1' with a 'Stopping...' status and a 'Lease expires: 14 days' message. On the right, a context menu is open for 'vApp etech1-01_1', listing actions: Open, Start, Suspend, Stop, Power Off, Reset, Discard Suspended State, Share..., Upgrade Virtual Hardware Version, and Delete (highlighted at the bottom).
3.	Click Yes to proceed  The screenshot shows two panels. On the left, a 'Delete vApp' dialog box asks 'Delete vApp etech1-01_1?' with 'Yes' and 'No' buttons; the 'Yes' button is highlighted. On the right, a 'Quick Access' panel shows instructions to start or use a vApp, a link to 'Add vApp from Catalog', and a red starburst graphic.

End of Lab