



Quick Installation Guide for the APG Smarts Client Tool

The client tool is intended for use on Windows workstation, to browse an APG report directly from SMARTS console. You must be running the client locally. Client tools only work when you are attached to the SAM. You can right click a device in the topology to view it in APG, or right click an event, to get historical view from APG.



The zip file contains 1 bat file:

Copy this file in the smarts client directory:


`{SMARTSHOME}\smarts\local\actions\client\`

Each of the script must be edit to provide your APG server hostname and http port.


Please, edit all .bat files, and make sure the path match your environment.

Then on your Smarts server, you have to configure from the Global-Manager-Console of your SAM, two new Client Tools.

Configuration of the first Client Tool (Full device visualization into APG):



Configuration of the second Client Tool (Visualization of a specific component):



Set context and status to filter as below:

